

FUJITSU Software Systemwalker Service Catalog Manager V15.3.2



Developer's Guide

B1WS-0985-07ENZ0(00) January 2015 **Trademarks**

LINUX is a registered trademark of Linus Torvalds.

Microsoft and Windows are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.

Oracle, GlassFish, Java, and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle Corporation and/or its affiliates.

Apache Ant, Ant, and Apache are trademarks of The Apache Software Foundation.

UNIX is a registered trademark of the Open Group in the United States and in other countries.

Other company names and product names are trademarks or registered trademarks of their respective owners.

Copyright (c) FUJITSU LIMITED 2010-2015

All rights reserved, including those of translation into other languages. No part of this manual may be reproduced in any form whatsoever without the written permission of FUJITSU LIMITED.

High Risk Activity

The Customer acknowledges and agrees that the Product is designed, developed and manufactured as contemplated for general use, including without limitation, general office use, personal use, household use, and ordinary industrial use, but is not designed, developed and manufactured as contemplated for use accompanying fatal risks or dangers that, unless extremely high safety is secured, could lead directly to death, personal injury, severe physical damage or other loss (hereinafter "High Safety Required Use"), including without limitation, nuclear reaction control in nuclear facility, aircraft flight control, air traffic control, mass transport control, medical life support system, missile launch control in weapon system. The Customer shall not use the Product without securing the sufficient safety required for the High Safety Required Use. In addition, FUJITSU (or other affiliate's name) shall not be liable against the Customer and/or any third party for any claims or damages arising in connection with the High Safety Required Use of the Product.

Export Restrictions

Exportation/release of this document may require necessary procedures in accordance with the regulations of your resident country and/or US export control laws.

Contents

	About this Manual	5
1	Introduction	8
1.1	The Developer's Tasks in CT-MG	8
1.2	Web Services Concepts	9
2	Platform Services	11
2.1	Purpose and Usage	11
2.2	Addressing the Platform Services	14
2.3	Authentication	15
3	Integrating Applications with CT-MG	17
3.1	Prerequisites	17
3.2.1 3.2.2 3.2.3	Implementing a Provisioning Service Implementing the Service as a Java Client Implementing the Service as a Non-Java Client Implementation Details	18
3.3	Adapting the Login/Logout Implementation	23
3.4	Integrating with CT-MG Event Management	28
3.5	Implementing Technical Service Operations	28
4	Integrating External Process Control	30
5	Integrating an External Parameter Configuration Tool	32
5.1	Cross-Document Messaging	32
5.2	Data Exchange	33
5.3	Overview of Tasks	37
6	Integrating Certificates for Trusted Communication	38
6.1	Introduction	38
6.2	Requirements for Web Service Calls from CT-MG	39
6.3	Requirements for Web Service Calls to CT-MG	40

6.4	Certificate Integration Procedures	41
6.4.1	Creating a Certificate and a Signing Request	41
6.4.2	Importing the Signed Certificates	42
6.4.3	Importing the CT-MG Server Certificate	43
Append	ix A Customer Billing Data	44
Append	ix B Revenue Share Data	61
B.1	Common Elements	61
B.2	Broker Revenue Share Data	62
B.3	Reseller Revenue Share Data	64
B.4	Marketplace Owner Revenue Share Data	67
B.5	Supplier Revenue Share Data	73
Glossar	v	81

About this Manual

This manual describes the public Web service interface of FUJITSU Software Systemwalker Service Catalog Manager - hereafter referred to as Catalog Manager (CT-MG) - and how to integrate applications and external systems with CT-MG.

The manual is structured as follows:

Chapter	Description
Introduction on page 8	Provides an overview of a developer's tasks, and describes the basic concepts of Web services.
Platform Services on page 11	Describes the CT-MG platform services as well as their purpose and usage.
Integrating Applications with CT-MG on page 17	Describes how to implement the interfaces between an application and CT-MG.
Integrating External Process Control on page 30	Describes how to integrate an external process control system with CT-MG.
Integrating an External Parameter Configuration Tool on page 32	Describes how to integrate an external parameter configuration tool with CT-MG.
Integrating Certificates for Trusted Communication on page 38	Provides an introduction to the usage of certificates for securing communication between CT-MG applications or external systems.
Customer Billing Data on page 44	Describes the elements of an XML file created by exporting customer billing data.
Revenue Share Data on page 61	Describes the elements of XML files created by exporting revenue share data.

Readers of this Manual

This manual is directed to developers who carry out tasks for different organizations involved in the usage of CT-MG, for example, integrate applications or external process control systems with CT-MG.

This manual assumes that you are familiar with the following:

- CT-MG concepts as explained in the Overview manual
- · Basic Web service concepts
- · XML and the XSD language
- · Web services standards SOAP and WSDL
- A programming language that can be used to create and invoke Web services, for example, Java
- · Java, Java servlets, and Java server pages
- Installation and basic administration of Web servers

Notational Conventions

This manual uses the following notational conventions:

Add	The names of graphical user interface elements like menu options are shown in boldface.
init	System names, for example command names and text that is entered from the keyboard, are shown in Courier font.
<variable></variable>	Variables for which values must be entered are enclosed in angle brackets.
[option]	Optional items, for example optional command parameters, are enclosed in square brackets.
one two	Alternative entries are separated by a vertical bar.
{one two}	Mandatory entries with alternatives are enclosed in curly brackets.

Abbreviations

This manual uses the following abbreviations:

APP Asynchronous Provisioning Platform

CT-MG Catalog Manager

CA Certification authority

laaS Infrastructure as a Service

JAX-WS Java API for XML Web services

JSP Java Server Pages
PaaS Platform as a Service

PSP Payment service provider
RPC Remote Procedure Calls
SaaS Software as a Service

SOAP Simple Object Access Protocol

WSDL Web Services Description Language

XSD XML Schema Definition

Available Documentation

The following documentation on CT-MG is available:

- Overview: A PDF manual introducing CT-MG. It is written for everybody interested in CT-MG and does not require any special knowledge.
- Online Help: Online help pages describing how to work with the administration portal of CT-MG. The online help is intended for and available to everybody working with the administration portal.

- Installation Guide (GlassFish): A PDF manual describing how to install and uninstall CT-MG. It is intended for operators who set up and maintain CT-MG in their environment.
- Operator's Guide: A PDF manual for operators describing how to administrate and maintain CT-MG.
- Technology Provider's Guide: A PDF manual for technology providers describing how to prepare applications for usage in a SaaS model and how to integrate them with CT-MG.
- Supplier's Guide: A PDF manual for suppliers describing how to define and manage service
 offerings for applications that have been integrated with CT-MG.
- Reseller's Guide: A PDF manual for resellers describing how to prepare, offer, and sell services defined by suppliers.
- Broker's Guide: A PDF manual for brokers describing how to support suppliers in establishing relationships to customers by offering their services on a marketplace.
- *Marketplace Owner's Guide:* A PDF manual for marketplace owners describing how to administrate and customize marketplaces in CT-MG.
- *Developer's Guide:* A PDF manual for application developers describing the public Web service interface of CT-MG and how to integrate applications and external systems with CT-MG.
- ServerView Resource Orchestrator Integration (GlassFish): A PDF manual for operators
 describing how to offer and use virtual platforms and servers controlled by ServerView
 Resource Orchestrator through services in CT-MG.
- Amazon Web Services Integration (GlassFish): A PDF manual for operators describing how
 to offer and use virtual servers controlled by the Amazon Elastic Compute Cloud Web service
 through services in CT-MG.
- OpenStack Integration (GlassFish): A PDF manual for operators describing how to offer and use virtual systems controlled by OpenStack through services in CT-MG.
- Javadoc documentation for the public Web service interface of CT-MG and additional resources and utilities for application developers.

1 Introduction

Catalog Manager (CT-MG) is a set of services which provide all business-related functions and features required for turning on-premise software applications into Software as a Service (SaaS) offerings and using them in the Cloud. This includes ready-to-use account and subscription management, online service provisioning, billing and payment services, and reporting facilities.

With its components, CT-MG covers all the business-related aspects of a Platform as a Service (PaaS) or Cloud platform. It supports software vendors as well as their customers in leveraging the advantages of Cloud Computing.

The basic scenario of deploying and using applications as services in the CT-MG framework involves the following users and organizations:

- **Technology providers** (e.g. independent software vendors) technically prepare their applications for usage in the Cloud and integrate them with CT-MG. They register the applications as technical services in CT-MG.
- **Suppliers** (e.g. independent software vendors or sales organizations) define service offerings, so-called marketable services, for the technical services in CT-MG. They publish the services to a marketplace.
- **Customers** register themselves or are registered by an authorized organization in CT-MG and subscribe to one or more services. Users appointed by the customers work with the underlying applications under the conditions of the corresponding subscriptions.
- **Marketplace owners** are responsible for administrating and customizing the marketplaces to which services are published.
- Operators are responsible for installing and maintaining CT-MG.

In extended scenarios, the suppliers who define marketable services may involve additional users and organizations in offering and selling these services:

- Brokers support suppliers in establishing relationships to customers by offering the suppliers' services on a marketplace. A service subscription is a contract between the customer and the supplier.
- Resellers offer services defined by suppliers to customers applying their own terms and conditions. A service subscription establishes a contract between the customer and the reseller

Developers in different organizations can use the CT-MG Web service interface for implementing applications that make use of CT-MG features or for integrating external systems with CT-MG.

1.1 The Developer's Tasks in CT-MG

As a developer, you integrate external applications and systems with CT-MG. You typically do this for the following organizations and purposes:

- Technology provider: You technically prepare applications for usage in a SaaS model and
 implement the services and interfaces required to integrate the applications with CT-MG.
 Depending on the application, this may involve: Implementing a provisioning service, adapting
 the application's login and logout behavior, providing for the generation and sending of events,
 implementing operations that can be carried out from CT-MG.
- Supplier or customer: You can integrate CT-MG with an external process control system
 in order to control the execution of specific CT-MG actions. This involves implementing a
 notification service which is invoked through appropriate triggers configured in CT-MG. The

triggers are defined and managed by the administrator of the affected organization. For details, refer to the CT-MG online help.

For performing these tasks, you use the public Web service interface of CT-MG. This interface, its documentation and additional resources, templates, samples, and utilities are provided in the CT-MG integration package (fujitsu-bss-integration-pack.zip file). A detailed documentation for these resources is provided as Javadoc. By opening the readme.htm file of the integration package, you can access the available Javadoc documentation as well as the resources themselves.

For supplier organizations, you can integrate an external tool for configuring service parameters with CT-MG. For performing the integration tasks, CT-MG provides a generic JavaScript interface. A sample and a JavaScript library that support you in integrating an external parameter configuration tool are provided in the CT-MG integration package (fujitsu-bss-integration-pack.zip file). By opening the readme.htm file of the integration package, you can directly access the sample and the library.

In order to provide for secure communication between CT-MG and the applications or external systems integrated with it, you can make use of certificates.

An additional task of a developer in the CT-MG context is the processing of billing data, for example, in an external accounting system. CT-MG allows suppliers, brokers, resellers, marketplace owners, and operators to export customer billing data and revenue share data to XML files. From these files, the required data can be extracted for further processing.

1.2 Web Services Concepts

A Web service is a software module performing a discrete task or a set of tasks that can be accessed and invoked over a network, especially the World Wide Web. A provider makes Web services available to client applications that want to use them. A client application can invoke Web services through remote procedure calls (RPC). A published Web service is described in a WSDL file that allows you to locate it and evaluate its suitability for your needs. As an example, a company could provide a Web service to its customers to check an inventory on products before they order them.

Web services as well as the client applications can be written in different languages and run on different platforms.

CT-MG provides its functionality as Web services. The public Web services as well as additional resources, templates, samples, and utilities can be used to integrate applications with CT-MG in order to make them available as services to customers.

The CT-MG Web services are written in Java using JAX-WS.

Web Services Standards

The development of Web services is based on the following standards:

• SOAP (Simple Object Access Protocol)

SOAP is a transport-independent messaging protocol. SOAP messages are XML documents that are sent back and forth between a Web service and the calling application. SOAP uses one-way messages, although it is possible to combine messages into request-response sequences. The SOAP specification defines the format of the XML message but not its content and how it is actually sent. However, the SOAP specification defines how SOAP messages are routed over HTTP.

The CT-MG Web services use SOAP for the XML payload (XML data part) and HTTP as the transport protocol for the SOAP messages. The CT-MG Web services support the SOAP 1.1 protocol.

WSDL (Web Service Description Language)
WSDL is an XML-based language used to define Web services and describe how to access them. Specifically, it describes the data and message contracts a Web service offers. By examining a Web service's WSDL document, developers know what methods are available and how to call them using the proper parameters.

For more information about SOAP and WSDL, refer to the SOAP and WSDL documents on the website of the World Wide Consortium website (www.w3c.org).

2 Platform Services

CT-MG exposes its basic functionality at a public Web service interface which consists of the so-called platform services. An application that integrates with CT-MG invokes the functionality of the platform services.

The following platform services are available:

- · Account management service
- Billing service
- Categorization service
- · Discount service
- · Event management service
- · Identification service
- Marketplace management service
- Reporting service
- Review service
- SAML service
- Search service
- · Service provisioning service
- · Session service
- Subscription management service
- · Tag service
- Trigger service
- Trigger definition service
- · VAT service

The platform services are available in the CT-MG integration package.

2.1 Purpose and Usage

This section contains a description of the purpose and usage of each platform service. For details on the methods of the services and the related data objects, refer to the Javadoc documentation.

Account Management Service

Java class name: com.fujitsu.bss.intf.AccountService

This service is used for managing the account data of organizations, including billing and payment information and custom attributes.

Billing Service

Java class name: com.fujitsu.bss.intf.BillingService

This service is used for exporting billing data and revenue share data.

Operators, suppliers, resellers, brokers, and marketplace owners can export customer billing data and revenue share data from CT-MG and process it using accounting, billing, and payment facilities that have already been established in their organization. This is useful, for example, to create invoices for customers who decide to pay on receipt of invoice, or for managing the revenue shares of the different organizations involved in offering and selling services.

The results of export operations are stored in XML files. For detailed information on the elements of the XML files, refer to *Customer Billing Data* on page 44 and *Revenue Share Data* on page 61.

Categorization Service

Java class name: com.fujitsu.bss.intf.CategorizationService

This service is used for defining and managing service categories.

A marketplace owner organization can create any number of categories for its marketplace. Suppliers, brokers, and resellers can assign these categories to the services they publish on the marketplace. Customers can use the categories for browsing the service catalog and searching for services on the marketplace.

Discount Service

Java class name: com.fujitsu.bss.intf.DiscountService

This service is used for retrieving discount values.

Event Management Service

Java class name: com.fujitsu.bss.intf.EventService

This service is used for recording events which are generated during the operation of applications that are integrated with CT-MG. Events can be used for billing and reporting. Examples of events are the completion of a specific transaction, or the creation or deletion of specific data.

For details on how to integrate an application with the CT-MG event management, refer to *Integrating with CT-MG Event Management* on page 28.

Identification Service

Java class name: com.fujitsu.bss.intf.IdentityService

This service is used for managing user accounts, user roles, and logins.

Marketplace Management Service

Java class name: com.fujitsu.bss.intf.MarketplaceService

This service is used for managing marketplaces and the marketable services published on them.

Reporting Service

Java class name: com.fujitsu.bss.intf.ReportingService

This service is used for retrieving a list of available reports.

CT-MG offers comprehensive reports for different purposes and at different levels of detail. Different types of report satisfy the needs of all participating parties. Reports can be displayed at the CT-MG user interface and exported to different file formats.

Review Service

Java class name: com.fujitsu.bss.intf.ReviewService

This service is used for creating and retrieving service reviews and ratings on a marketplace.

SAML Service

Java class name: com.fujitsu.bss.intf.SamlService

This service is used for the SAML-based single sign-on mechanism. It creates a SAML 1.1 assertion based on the credentials of the logged-in user, which can be sent to a service provider or application to grant access to specific resources. To use the SAML-based single sign-on mechanism for an application integrated with CT-MG, the user access type must be defined and implemented for it. For details on access types, refer to the *Technology Provider's Guide*.

Search Service

Java class name: com.fujitsu.bss.intf.SearchService

This service is used for searching for services published on a marketplace.

Service Provisioning Service

Java class name: com.fujitsu.bss.intf.ServiceProvisioningService

This service is used for managing technical and marketable services in CT-MG in order to make applications available in service offerings.

Session Service

Java class name: com.fujitsu.bss.intf.SessionService

This service is used for storing, retrieving, and deleting CT-MG session data. If you need to implement your own token handler and logout listener for an application integrated with CT-MG, you have to implement calls to methods of this service. For details, refer to *Adapting the Login/Logout Implementation* on page 23.

Subscription Management Service

Java class name: com.fujitsu.bss.intf.SubscriptionService

This service is used for managing subscriptions. Depending on the instance provisioning mechanism of your applications integrated with CT-MG, you may have to implement calls to methods of this service in the provisioning service. For details, refer to *Implementation Details* on page 20.

Tag Service

Java class name: com.fujitsu.bss.intf.TagService

This service is used for retrieving the tags (search terms) of the tag cloud of a marketplace. The tag cloud is the area of a marketplace containing defined search terms (tags).

The operator can set a value for the maximum number of tags composing the tag cloud, and the minimum number of times a tag must be used in services to be shown in the tag cloud. The more often a specific tag is used for services, the bigger the characters of the tag are displayed at the user interface.

Trigger Service

Java class name: com.fujitsu.bss.intf.TriggerService

This service is used for retrieving and manipulating trigger process data. These data are used in a notification service to approve or reject CT-MG actions in a process control system. For details on how to integrate external process control systems, refer to *Integrating External Process Control* on page 30 and the online help.

Trigger Definition Service

Java class name: com.fujitsu.bss.intf.TriggerDefinitionService

This service is used for managing the definitions of triggers which are used to interact with external process control systems. The triggers are defined and managed by the administrator of the affected organization. For details, refer to the CT-MG online help.

VAT Service

Java class name: com.fujitsu.bss.intf.VatService

This service is used for handling VAT-related tasks.

Suppliers can enable VAT rate support for their services and customers in order to invoice usage charges for subscriptions as gross prices. The suppliers are responsible for setting the correct VAT rates. For details on billing and payment, refer to the *Supplier's Guide*.

2.2 Addressing the Platform Services

Once deployed, the platform services can be addressed via WSDL URLs. In the application server administration console, the fujitsu-adm-um-webservices.jar subcomponent of the fujitsu-bss application includes a descriptor file with all the information needed for finding out the WSDL URL of a platform service:

- In the GlassFish administration console, go to Common Tasks -> Applications -> fujitsu-bss.
- 2. On the **Descriptor** tab, open the META_INF/sun-ejb-jar.xml descriptor file of the fujitsu-adm-um-webservices.jar **subcomponent**.

For every Web service, the endpoint address URI shows the Web service name, its version, and whether it is to be addressed through basic authentication (BASIC), certificate-based authentication (CLIENTCERT), or a security token service (STS). Refer to the next section for details on the authentication types.

The URL pointing to the WSDL definition of a platform service is constructed as follows:

```
<BASE URL HTTPS>/<endpoint-address-uri>?wsdl
```

where

 ${\tt <BASE_URL_HTTPS>}$ points to the server and port where the platform services have been deployed.

?wsdl is the suffix to be used for identifying a WSDL file.

Example: https://myserver:8081/AccountService/v1.6/BASIC?wsdl

Service Versions

A Web service user accesses exactly one version of the Web service interface. The current versions of the platform services and the other Web service APIs of CT-MG are the following:

Platform services: v1.6 Notification service API: v1.7 Provisioning service API: v1.5 Operation service API: v1.3 PSP integration service API: v1.6

Technical service definition of an application: v1.5

2.3 Authentication

CT-MG can be installed in two modes. The mode determines how users and Web services are authenticated:

CT-MG is installed as a platform for public access from anywhere in the Internet. Users are
authenticated with CT-MG and can be managed in CT-MG or an existing LDAP system of an
organization. Web service calls are formatted as SOAP messages and are authenticated in
CT-MG either by providing a user ID and password in their header, or by certificates.

This authentication mode is referred to as INTERNAL.

 CT-MG is installed as a SAML 2.0 service provider. SAML (Security Assertion Markup Language) is an XML-based protocol that uses SAML assertions to pass information about a user between a SAML IdP and a SAML service provider (CT-MG). With SAML 2.0, Web browser single sign-on within a company is provided.

All users and Web service calls are authenticated against the authentication system underlying the IdP, for example, OpenAM, Cloudminder, or Active Directory. The IdP provides a Web browser single sign-on profile (SSO profile) and a Security Token Service (STS). This is a Web service that issues security tokens as defined in the WS-Security/WS-Trust specification. A connection to the IdP is always established by the client (Web browser or Web service application), not by CT-MG. The client sends a request for a SAML assertion. The IdP returns an assertion authenticating the calling user.

The user data is managed in the IdP. Additionally, all users who are to work with CT-MG must be registered explicitly in CT-MG.

This authentication mode is referred to as SAML SP.

Every application integrated with CT-MG or accessing the platform services acts as a Web service client. CT-MG acts as the server, and the client must provide its authenticating data to the server. Three options are available:

Basic authentication:

The caller sends the key and password of a CT-MG user and addresses the CT-MG Web services with the BASIC suffix.

Basic authentication can only be used if CT-MG is installed in INTERNAL authentication mode. It must be used for calling CT-MG functions that require the specification of a user role. The user role determines whether the user is allowed to execute the function.

Certificate-based authentication:

The caller provides a certificate to the CT-MG server. It addresses the CT-MG Web services with the CLIENTCERT suffix. In this case, the following requirements must be fulfilled:

- The distinguished name (DN) of the client's certificate must correspond to the distinguished name (DN) configured and stored in CT-MG for the corresponding organization.
- CT-MG must trust the client's certificate: The CT-MG truststore must contain a certificate with a valid signing chain to the certificate presented by the client.

Certificate-based authentication can be used in both authentication modes (INTERNAL and SAML_SP). It must be used when integrating a PSP such as Heidelpay. Web services calling PSP-related functions of CT-MG do not require the specification of a user role.

Refer to *Integrating Certificates for Trusted Communication* on page 38 for details on how to install and handle the certificates required.


Security token service authentication:

The caller addresses the CT-MG Web services with the STS suffix.

Web service calls are authenticated by means of a security token service (STS). This is a Web service that issues security tokens as defined in the WS-Security/WS-Trust specification. WS-Security (Web Services Security) is an extension to SOAP to apply security to Web services. The protocol specifies how integrity and confidentiality can be enforced on messages and allows the communication of various security token formats, such as SAML, Kerberos, and X.509. Its main focus is the use of XML Signature and XML Encryption to provide end-to-end security. WS-Security incorporates security features in the header of a SOAP message.

Security token service authentication can only be used if CT-MG is installed in SAML_SP authentication mode so that it acts as a SAML 2.0 service provider.

The following picture illustrates the communication between a Web service client, CT-MG and an STS:



- 1. The Web service client connects to CT-MG and accesses the endpoint of a platform service. In the example above, this is the AccountService.
- 2. CT-MG returns a WSDL file containing security information. The WSDL file also contains the URL for connecting to the STS.
- 3. The Web service client connects to the STS and requests a security token.
- 4. The STS returns a SAML token authenticating the calling user.
- 5. The STS token is sent to CT-MG, the application server validates the token, then CT-MG validates the user ID provided with the token, and the requested operation can be executed.

3 Integrating Applications with CT-MG

Integrating an application with CT-MG involves the following implementation tasks:

- · Implement a provisioning service
- · Adapt the login/logout implementation
- Integrate the application with the CT-MG event management
- · Implement service operations

The sections of this chapter describe the required implementation steps in detail.

3.1 Prerequisites

Before you can start integrating an application with CT-MG, you have to set up your development environment. The following prerequisites must be fulfilled:

- You have installed a servlet container or application server, where you can deploy your application and the provisioning service, if any.
- You have installed a Web service framework, for example JAX-WS (Java API for XML Web Services), to deal with the Web services.
 - JAX-WS is a Java API for creating and using Web services. It is part of the Java EE platform from Oracle.
- You have decided on the authentication type to be used. For details refer to *Authentication* on page 15.

3.2 Implementing a Provisioning Service

As a first integration step, you implement a so-called provisioning service that exposes its operations as a Web service. A provisioning service is required for integrating an application with the subscription management of CT-MG. The provisioning service is called by CT-MG when customers subscribe to a service and manage their subscriptions. Additionally, the provisioning service may be called for creating and managing users.

You do not need to implement a provisioning service if you have chosen to use the external access type. With this access type, users access an application directly after subscribing to a corresponding service. They are redirected immediately to the underlying application. Any further interaction takes place directly between the user and the application without involving CT-MG in any way.

For the implementation of a provisioning service, you need to consider the following:

Instance provisioning

When a customer subscribes to a service, the underlying application is supposed to perform specific steps required for the subscription and return an identifier to CT-MG for future reference. The term 'instance' denotes all the items that the application has provisioned for a subscription.

The actions to be performed and the items to be created, if any, depend entirely on the concepts and functionality of your application. For example, if a customer creates and stores data when using your application, your application may create a separate workspace in a data container or a separate database instance.

Provisioning mode

Instance provisioning can be performed in synchronous or asynchronous mode.

Synchronous mode is used if provisioning can be completed right away. The provisioning service triggers the application to perform all the required actions and confirms the operation as complete. CT-MG then sets the subscription to active, which means that the service is ready to be used by the customer.

Asynchronous mode is used if provisioning operations take a long time because long-running processes or manual steps are involved, or when huge amounts of data or virtual machines need to be set up. In this case, the provisioning service notifies CT-MG that the provisioning is pending. Required actions may have started on the application side, but have not been completed yet. The provisioning service needs to notify CT-MG using the subscription management service when provisioning is either complete or cannot be completed.

CT-MG supports the development of asynchronous provisioning services with the asynchronous provisioning platform (APP). This is a framework which provides a provisioning service as well as functions, data persistence, and notification features which are always required for integrating applications in asynchronous mode. The framework, samples, and documentation are provided in the integration package for asynchronous provisioning (fujitsu-bss-integration-app-pack.zip file).

Application parameters

An application may have parameters that are of relevance for the service provisioning in CT-MG. Parameters can be used to define different feature configurations or service restrictions, for example, the maximum number of folders, files, or objects that can be created. Application parameters are specified in the technical service definition.

CT-MG can pass parameters to your application through the instance provisioning call. Any further processing must be carried out by your application. Especially if parameters are used to impose restrictions on service usage, the application needs to ensure that the restrictions are met. For example, if there is a parameter to restrict the maximum number of files created for a subscription, the application needs to track the actual number and ensure that the maximum number is not exceeded.

For details on how to define parameters in the technical service definition, refer to the *Technology Provider's Guide*.

User management

If users access your application through CT-MG, you need to implement user management operations. These operations are called when users are assigned to or deassigned from a subscription in CT-MG, or when user profiles are updated. Your application may take corresponding actions, for example, create corresponding user accounts in its own user management system.

To implement a provisioning service, you have two options:

- Implementing the service as a **Java client** (see *Implementing the Service as a Java Client* on page 18)
- Implementing the service as a **non-Java client** (see *Implementing the Service as a Non-Java Client* on page 20)

3.2.1 Implementing the Service as a Java Client

It is recommended to use the JAX-WS framework for implementing a provisioning service. CT-MG ships the Java interfaces for its Web services as a .jar file. You can directly write your Java code and include this .jar file for calls from CT-MG to the application (outbound calls), or

implement the Java interfaces for calls from the application to CT-MG (inbound calls). No code generation is required.

Both call directions can be deployed in Java EE environments:

Outbound calls:

For outbound Web service calls, JAX-WS offers APIs to directly address a Web service specified by a WSDL file and to obtain a proxy implementation of the interface.

The following code creates a client for the Web service with a given WSDL:

Inbound calls:

Providing a Web service implementation that can be used for inbound calls means that you implement the service and annotate the implementation to get published.

If the application is deployed in a Java EE-compliant application server, the provisioning service can be deployed as an annotated bean. The service implementation can be either a stateless session bean when deployed as J2EE application, or a plain Java object when deployed as part of a Web application. In both cases, the annotation is <code>javax.jws.WebService</code> with a reference to the service definition.

Your provisioning service must implement the provisioning API of CT-MG, for example, as shown here:

Note that the target namespace must be exactly the same as defined in the interface.

The <code>endpointInterface</code> attribute refers to the Java interface defining the Web service. This allows the implementation class to provide the respective Java method implementations. All Web service-related annotations are taken from the interface.

If the application is a Java application but not deployed in a Java EE-compliant application server, JAX-WS offers APIs to publish the Web services:

```
import javax.xml.ws.Endpoint;
public static void main(String[] args) {
    Endpoint.publish(
        "https://www.example.com/MyService/provisioningServices",
        new MyProvisioningServiceImpl());
```

}

3.2.2 Implementing the Service as a Non-Java Client

Non-Java clients need to conform to the WSDL and XSD files shipped with CT-MG: You create a Web service based on the ProvisioningService.wsdl document.

Depending on the platform and the Web services framework you are using, code generation will be required or dynamic usage will be possible. For example, dynamic languages like PHP or Python allow generating proxy object instances directly from a WSDL at runtime.

3.2.3 Implementation Details

The following steps provide an overview of the methods you need to implement for a provisioning service.

Note: If you are using the asynchronous provisioning platform for developing a provisioning service, you do not need to implement these methods. Instead, you develop a service controller.

For details, refer to the documentation provided with the integration package for asynchronous provisioning (fujitsu-bss-integration-app-pack.zip file).

- 1. Implement at least the following methods:
 - createInstance for the synchronous provisioning of an instance or asyncCreateInstance for the asynchronous provisioning of an instance.
 - deleteInstance
- 2. If your application has parameters that are set during instance provisioning, implement the modifySubscription Or asyncModifySubscription method.
- 3. If your application allows for upgrading or downgrading to another application instance, implement the upgradeSubscription or asyncUpgradeSubscription method.
- 4. If users access your application through CT-MG, implement the following methods:
 - createUsers
 - deleteUsers
 - updateUsers
- 5. If you are using asynchronous instance provisioning (asyncCreateInstance), you need to implement calls to the following methods of the subscription management service (see *Platform Services* on page 11):
 - abortAsyncSubscription
 - completeAsyncSubscription
- 6. If you implement the asyncModifySubscription method, you need to implement calls to the following methods of the subscription management service (see *Platform Services* on page 11):
 - abortAsyncModifySubscription
 - completeAsyncModifySubscription

- 7. If you implement the asyncUpgradeSubscription method, you need to implement calls to the following methods of the subscription management service (see *Platform Services* on page 11):
 - abortAsyncUpgradeSubscription
 - completeAsyncUpgradeSubscription
- 8. Deploy your provisioning service and make sure that it is operational.

For each organization role, the following tables list the methods of the provisioning service which are called when specific user actions are executed in CT-MG. The dependencies on the chosen access type and other parameters are also described, if applicable.

For details on access types, refer to the Technology Provider's Guide.

Technology Provider

User Action	Method	Behavior
Import service definition Click a service entry to view the details in the CT-MG administration portal.	sendPing()	sendPing() is called for all access types except external.

Supplier/Reseller/Broker

User Action	Method	Behavior
Terminate a subscription	deleteInstance()	deleteInstance() is called for each deleted subscription and for all access types except external.
Activate or deactivate services Activate a service.	sendPing()	sendPing() is called for all access types except external.
Manage payment types Deactivate/reactivate a payment type for a customer.	<pre>deactivateInstance() activateInstance()</pre>	deactivateInstance() and activateInstance() are called for all access types except external. deactivateInstance() is called if the customer uses the deactivated payment type to pay for his subscriptions. activateInstance() is called if a deactivated payment type used by the customer is made available again. The methods are called for each affected subscription.

Customer

User Action	Method	Behavior	
Subscribe to a service	<pre>createInstance() asyncreateInstance()</pre>	createInstance() is called for login, direct, and user access in synchronous mode.	
		asyncreateInstance() is called for login, direct, and user access in asynchronous mode.	
		A list of all parameters and values of a service can be retrieved with the getParameterValue() method of the InstanceRequest class.	
Manage Users Modify user profiles, no	updateUsers()	updateUsers() is called for login and user access.	
changes in assignments to subscriptions		The method is called independent of any changes in the user profile.	
Assign users to a subscription	createUsers()	createUsers() is called for login and user access.	
Assign one or more users to the selected subscription		The method is called for each assigned user. The users parameter contains the list of users who are to be assigned to the selected subscription.	
Deassign users from a subscription	deleteUsers()	deleteUsers() is called for login and user access.	
Deassign one or more users from the selected subscription		The method is called for each deassigned user. The users parameter contains the list of users who are to be deassigned from the selected subscription.	
Modify a subscription	modifySubscription() asyncModifySubscription()	modifySubscription() is called in synchronous mode for all access types except external.	
		asyncModifySubscription() is called in asynchronous mode for all access types except external. The method is called when customizable parameters or the subscription ID are changed by the customer.	

User Action	Method	Behavior
Up/Downgrade a subscription	upgradeSubscription() asyncUpgradeSubscription	upgradeSubscription() is called in synchronous mode for all access types except external.
		asyncUpgradeSubscription() is called in asynchronous mode for all access types except external.
		The method is called when a customer upgrades or downgrade a subscription.
Terminate a subscription	deleteInstance()	deleteInstance() is called for all access types except external.

If a subscription expires, the <code>deactivateInstance()</code> method is called and the instances related to the subscription are deactivated. If the subscription is updated and activated again, the <code>activateInstance()</code> method is called.

For details on the methods and data objects, refer to the Javadoc for the CT-MG provisioning API shipped in the CT-MG integration package.

3.3 Adapting the Login/Logout Implementation

If you opt for access through CT-MG (login access), you need to adapt the login/logout implementation of your application to pass the control and authentication of users from the application to CT-MG, and implement the relevant methods defined by the provisioning service.

The required functionality for login and logout is distributed between a token handler, a custom login module, a custom logout module, and a logout listener:

- The **token handler** is responsible for requesting CT-MG to resolve a user token into a user ID. It takes up the task of creating a session object and storing the user ID in that object. Additionally, it forwards requests containing a resolved user token to the custom login module.
- The custom login module passes the user ID to the application. It enables users to log in to
 the application without requesting any further credentials. Users are trusted because they have
 already been authenticated by CT-MG. For example, a custom login module might pass the
 user ID and a default password to the application.
 - To ensure that any login takes place through CT-MG, the direct login to your application must be bypassed. For this purpose, you have to implement the required interface methods between the application and CT-MG.
- The custom logout module closes user sessions on the application side and redirects users
 to the logout page of CT-MG. The URL of the logout page is returned to the application by the
 deleteServiceSession method of the CT-MG session service.
- The logout listener notifies CT-MG when a user logs out or a session timeout occurs.

As for the custom login and logout modules, you need to analyze the existing functionality of your application and adapt it to match the required behavior.


CT-MG provides resources for J2EE environments that support you in adapting the login/logout implementation of a Java-based Web application. The resources are called **integration helpers** and contain a ready-to-use token handler and logout listener.

The integration helpers can be used with any Java-based Web application. The token handler is implemented as a Java servlet and as a JSP; the logout listener is implemented as a session listener.

If your application is based on a different technology, you need to implement your own token handler and logout listener by calling the following methods of the platform session service (see *Platform Services* on page 11):

- resolveUserToken for requesting CT-MG to resolve a user token
- deleteServiceSession for notifying CT-MG of a logout or session timeout

The following figure illustrates how login access works and which parts have to be added or adapted in the login/logout implementation of your application (components provided by CT-MG including the integration helpers are shown in gray):



The integration helpers are contained in the integrationhelper subfolder of the CT-MG integration package (fujitsu-bss-integration-pack):

• fujitsu-bss-webservices-proxy.jar: A library containing a Web service proxy for INTERNAL and SAML_SP authentication mode. This proxy is implemented in Java and ready

to be used. It creates a Web service proxy containing all information required to establish a connection with a CT-MG Web service.

- Integrationhelper.jar: A library containing a token handler and logout listener. They are also implemented in Java and ready to be used.
- Integrationhelper.war: A Web archive including the above integration helpers and additional resources required by them.
- IntegrationhelperSRC.zip: An archive file containing the source code of the integration helpers.

The Integrationhelper.war package has the following contents:

Package Contents	Description	
Tokenhandler.jsp	Token handler, welcome and logout page	
Logout.jsp	implemented as Java server pages (JSP).	
Welcome.jsp		
WEB-INF/web.xml	A sample configuration file with entries for the token handler servlet and the logout listener.	
WEB-INF/lib	A folder containing all JAR files required by the CT-MG integration helpers.	
WEB-INF/classes	A folder containing the ready-to-use logout listener class:LogoutListener.class.	
WEB-INF/classes/ tokenhandler.properties	A property file specifying the information needed to access the CT-MG platform services and the relative URL to the custom login module of your application. The custom login module must be on the same machine and in the same context as the token handler.	

To integrate the CT-MG integration helpers into your Web application:

- 1. Extract the Integrationhelper.war package from the CT-MG integration package to a location of your choice, or add the Integrationhelper.jar and fujitsu-bss-webservices-proxy.jar packages to the class path of your application.
- 2. Configure the tokenhandler.properties file and enter the following information:
 - The URL of the WSDL file of the platform's session service:
 - The authentication mode in which CT-MG is installed determines which CT-MG Web services are to be addressed:
 - In INTERNAL authentication mode these are the Web services with the BASIC, in SAML_SP mode, these are the Web services with the STS suffix. In case, certificate-based authentication is used, the Web services with the CLIENTCERT suffix are used, and it is irrelevant whether CT-MG runs in INTERAL or SAML_SP authentication mode.
 - Server and port where the CT-MG platform services have been deployed, as well as the current Web services version.

- Depending on the authentication mode in which CT-MG is installed: ID or key as well as
 password of the calling user. The user must have the role of a technology manager in a
 technology provider organization.
- Path to the JSP page or servlet to be used as the FORWARD target after the user token has been resolved.
- 3. Copy the contents of the WEB-INF/lib and WEB-INF/classes folders to the corresponding folders of your Web application.
- 4. Do one of the following:
 - If you want to use the JSP-based token handler, copy the Tokenhandler.jsp file to your Web application.
 - If you want to use the servlet-based token handler, register it in the web.xml file of your Web application.
 - To do this, you can copy the <code>servlet</code> and <code>servlet-mapping</code> sections from the sample <code>web.xml</code> file, which is part of the <code>Integrationhelper.war</code> package, to the <code>web.xml</code> file of your Web application.
- 5. Register the logout listener in the web.xml file of your Web application.

 To do this, you can copy the listener section from the sample web.xml file, which is part of the Integrationhelper.war package, to the web.xml file of your Web application.
- 6. In the technical service definition of the application, the path to the token handler must be specified in the <code>loginPath</code> attribute for login access.
 - For details on the technical service definition, refer to the *Technology Provider's Guide*.

Example

Suppose you implemented a servlet-based custom login module for your application, which is to be called after the user token has been resolved. The custom login module is available as a Web resource as a <code>DoAutoLoginServlet</code> servlet at <code>/DoAutoLogin</code>. Your Web application is running on <code>myserver</code> at port 7777 using the context <code>myapplication</code>. The CT-MG platform services are listening at port 8081. CT-MG is installed in SAML_SP mode.

Depending on whether you use the servlet-based or the JSP-based token handler, the configuration files look as shown below:

Servlet-Based Token Handler

· tokenhandler.properties

```
BSS_AUTH=SAML_SP
BSS_HOST=myserver
BSS_PORT=8081
BSS_SERVICE_VERSION=v1.6
BSS_NAMESPACE_URI=http://SessionService/xsd/v1.6

BSS_USER_ID=User1
BSS_PWD=myPassword
FORWARD=/Welcome.jsp
```

web.xml

```
<servlet-name>TokenhandlerServlet</servlet-name>
   <servlet-class>com.fujitsu.bes.integrationhelper.TokenhandlerServlet
   </servlet-class>
</servlet>
<servlet-mapping>
   <servlet-name>TokenhandlerServlet</servlet-name>
   <url-pattern>/resolveToken</url-pattern>
</servlet-mapping>
   <servlet-name>DoAutoLoginServlet</servlet-name>
   <servlet-class>servlets.DoAutoLoginServlet
   </servlet-class>
</servlet>
<servlet-mapping>
   <servlet-name>DoAutoLoginServlet</servlet-name>
   <url-pattern>/doAutoLogin</url-pattern>
</servlet-mapping>
stener>
<listener-class>com.fujitsu.bes.integrationhelper.LogoutListener
   </listener-class>
</listener>
```

Technical service definition

```
...
<TechnicalService
  id="SampleService"
  baseUrl="https://myserver:7777/myservice"
  loginPath="/resolveToken"
  ...
>
```

JSP-Based Token Handler

tokenhandler.properties

```
BSS_AUTH=SAML_SP
BSS_HOST=myserver
BSS_PORT=8081
BSS_SERVICE_VERSION=v1.6
BSS_NAMESPACE_URI=http://SessionService/xsd/v1.6

BSS_USER_ID=User1
BSS_PWD=myPassword

FORWARD=/DoAutoLogin
```

web.xml

Technical service definition

```
...
<TechnicalService
  id="SampleService"
  baseUrl="https://myserver:7777/myservice"
  loginPath="/Tokenhandler.jsp"
  ...
>
```

3.4 Integrating with CT-MG Event Management

The event management service in CT-MG collects specific events generated during application operation. These events can be used for price models, billing, and reporting. Examples of events are the completion of a specific transaction, or the creation or deletion of specific data.

Your application can send events to CT-MG at runtime through the event management service, which is one of the CT-MG platform services.

To integrate an application with CT-MG event management:

- 1. If your application does not generate the required events yet, implement the generation of events.
- 2. Depending on the information available for a subscription, implement the sending of events to CT-MG by calling one of the following methods of the event management service (see *Platform Services* on page 11):
 - recordEventForSubscription (subscription key must be specified)
 - recordEventForInstance (ID of the technical service and instance ID must be specified) For details on the methods, refer to the Javadoc for the CT-MG platform services.
- 3. When preparing the technical service definition, declare the events that your application will send.

Note: CT-MG comes with two predefined events, which can be used with login access: login to a service and logout from a service. These events are generated automatically and need not to be implemented in the application or defined in the technical service definition. To use the logout event, you must implement a logout listener. For details refer to *Adapting the Login/Logout Implementation* on page 23.

3.5 Implementing Technical Service Operations

You may wish that your technical service offers additional operations or functions that are to be accessible via the CT-MG user interface. In a SaaS environment, applications are not installed locally but provisioned as services. Therefore, users cannot access the system resources the applications are using, for example, to perform administrative tasks such as system backup or shutdown. Technical service operations can be used to access the resources of an application and perform administrative tasks without actually opening the application.

To provide technical service operations, a Web service based on the operation service API must be implemented. The operations, their parameters, and the access information of the Web service must be specified in the technical service definition for the application. For details, refer to the *Technology Provider's Guide*.

To integrate a technical service operation:

1. Implement the executeServiceOperation() and the getParameterValues() methods in a Web service definition using the OperationService interface of the operation API, which is part of the CT-MG integration package.

The following information is provided as parameter settings for the executeServiceOperation() method:

- The user identifier. This ID is unique in the instance context and allows the technical service to perform built-in security checks.
- The instance identifier. This ID uniquely identifies the application instance that is to be affected by the operation.
- For asynchronous operations: The transaction identifier. This ID uniquely identifies the transaction to be executed.
- The operation identifier. This ID uniquely identifies the operation to be executed as defined in the technical service definition. For details, refer to the *Technology Provider's Guide*.
- Parameters. This is the list of parameters and their values as retrieved with the <code>getParameterValues()</code> method or depending on the type of parameter their specified values. The parameters must also be defined in the technical service definition. For details, refer to the *Technology Provider's Guide*.

You need to provide the operation in a WSDL file that is accessible by a URL.

2. Edit the technical service definition XML file and include the operation and its parameters. For details, refer to the *Technology Provider's Guide*.

When implementing service operations, be aware of the following:

- The return type is not configurable; currently it can only be of type <code>operationResult</code>.
- CT-MG does not provide access control. Every user who can use the subscription can also execute the operations.
- The operations can be executed in synchronous or asynchronous mode. The transaction mode is defined in the <code>OperationResult</code> class of the <code>OperationService</code> interface.
- For allowing users to view the status of asynchronous service operations, implement the updateAsyncOperationProgress() method using the SubscriptionService interface of the CT-MG public Web service API.

4 Integrating External Process Control

Organizations often have specific processes for registering users, subscribing to services, or defining prices. Usually, such processes include approval processes and are modeled and automated with a process control system.

Certain actions of customers and suppliers can be carried out under the control of an external process control system. You can configure so-called triggers which are invoked when these actions are carried out. The triggers start the corresponding process in the process control system. If approval for the action is required, it is suspended until it is approved or rejected in the process control system. If no approval is required, the action is instantly executed.

As a prerequisite for controlling actions by processes, a notification service must exist and be deployed. This service forms the interface between the platform and the process control system.

Users can see all pending actions at the CT-MG user interface, cancel them, or delete aborted ones.

Process-Controlled Actions

The following actions may be subject to process control and thus to approval in an external process control system before they are executed in CT-MG:

- For any type of organization, the following triggers can be configured:
 - A subscription is to be changed, for example, renamed (Modify subscription).
 - A billing run is completed, and the billing data for a billing period is calculated (Billing run finished).
 - A subscription is to be added (Subscribe to service).
 - A user is to be assigned to or removed from a subscription (Assign users to subscription).
 - A subscription is to be upgraded or downgraded (Up/Downgrade subscription).
 - A subscription is to be terminated (Terminate subscription).
 - A user is to be registered (Register user).

Triggers can only be configured for registering single users. The import of multiple users in one operation from an LDAP system or a user data file cannot be executed under process control.

- For suppliers, the following additional triggers can be configured:
 - A customer is to be registered (Register customer).
 - The payment types for a customer are to be changed (Manage payment types for customer).
 - A marketable service is to be activated (Activate service).
 - A marketable service is to be deactivated (Deactivate service).
 - A user of an organization subscribes to a service offered by the supplier (Subscription created (any user)).
 - A user of a customer modifies a subscription to a service of the supplier (Subscription modified (any user)).
 - A user of a customer terminates a subscription to a service of the supplier (Subscription terminated (any user)).

Connecting to an External Process Control System

If you want CT-MG to connect to an external system to handle notifications and thus make use of the trigger processing feature of CT-MG, the following steps are required:

- 1. Implement a notification service:
 - An external system that is to be notified about certain actions must implement a Web service for the <code>com.fujitsu.bss.notification.intf.NotificationService</code> interface. This interface and the required data objects are provided with the CT-MG integration package.
- 2. Deploy the notification service in your environment. You can do this on the system hosting the process control system you want to use, or on any other system.
- 3. Configure the relevant triggers in CT-MG. To do this, you must be an administrator of your organization in CT-MG.
 - When defining a trigger, you need to provide the URL of the notification service WSDL file, for example: https://myServer:8280/NotificationService?wsdl.
 - For details on how to define and manage triggers in CT-MG, refer to the CT-MG online help.
 - As soon as the notification service is deployed and the process triggers have been configured in CT-MG, every action for which a process trigger has been configured results in a notification to your notification service. A trigger process key is sent for all actions that require a callback from the external system. This key is necessary to approve or reject an action.
 - The process triggers are queued and executed asynchronously. They are not called inside the transaction initiated by the user.
- 4. For approval or rejection, the process control system needs to call one of the methods provided by the trigger service (see *Platform Services* on page 11), and send its response back to CT-MG. As a result, the interrupted action is continued or canceled. When rejecting an action, the reason for the rejection can be passed.

5 Integrating an External Parameter Configuration Tool

A supplier organization can integrate a third-party or proprietary tool for configuring service parameters with CT-MG. The tool can be used by the supplier's customers for defining and updating the parameters of a service. It replaces the default user interface for configuring service parameters on a marketplace.


CT-MG allows for a seamless integration of the tool. A generic JavaScript interface is provided by which supplier organizations can integrate a tool of their choice. The following basic concepts are relevant:

- Cross-document messaging is used for the communication between CT-MG and an external parameter configuration tool.
- · The exchange of data is based on JavaScript Object Notation (JSON).

The sections of this chapter describe the basic concepts and give an overview of the required implementation tasks of a developer.

5.1 Cross-Document Messaging

The following illustration shows how CT-MG uses cross-document messaging for the communication with a parameter configuration tool:



Cross-document messaging is a JavaScript API which enables communication between documents from different origins or source domains. With the methods of this API, scripts can interact across domain boundaries and send plain text messages from one domain to another. Cross-document messaging can be used in all Web browsers supported by the CT-MG user interface.

User action in a Web browser (client) initiates cross-document messaging:

- When subscribing to a service or updating a service on a marketplace, a customer clicks
 Configure to specify the service parameters. This is the trigger for loading a modal window in
 the Web browser:
 - The lower part of the modal window is an inline frame element (<iframe>) which links the external parameter configuration tool with CT-MG. The HTML page of the tool is the source of the frame.
 - The upper part of the window outputs error messages in case the validation of an HTTP response from the tool fails.
- 2. The Web browser sends an HTTP request to the Web server where the external parameter configuration tool is deployed to load the HTML page of the tool into the inline frame element.
- 3. As soon as the HTML page of the external parameter configuration tool is loaded, the Web browser receives the first message from the tool, the initialization message. This confirms that the communication is enabled. The HTML page of the tool is displayed in the Web browser.

CT-MG delivers a sample JavaScript tool that you can integrate with CT-MG to see how cross-document messaging can be implemented. For information on the resources that support you in integrating a parameter configuration tool, refer to *Overview of Tasks* on page 37.

5.2 Data Exchange

CT-MG specifies the data structures that can be exchanged during the parameter configuration process with an external tool. Based on the service parameters that are defined for the underlying technical services, CT-MG specifies:


- The input data structures that are sent from CT-MG to the parameter configuration tool.
- The output data structures that must be returned to CT-MG by the parameter configuration tool.

CT-MG uses JavaScript Object Notation (JSON) as data-interchange format. JSON offers an open standard data format that is language-independent and primarily used for transmitting text messages between Web applications.

Note: The parameter configuration tool must support JSON to exchange data with CT-MG. It is up to the tool how the text messages are encoded and decoded. The tool must not necessarily be a JavaScript application.

Message Types

The configuration process with an external tool consists of three types of messages: INIT MESSAGE, CONFIG REQUEST, and CONFIG RESPONSE.



An **initialization message** is sent from the external tool to CT-MG as soon as the configuration process is triggered by a user action in the Web browser (client). The JSON message defines the height and width of the inline frame element that is used for loading the external HTML page in CT-MG. The message is the trigger for displaying the modal window with the external HTML page. It instantiates the external parameter configuration tool.

When the initialization message is received, a **configuration request** is sent from CT-MG to the external tool. This JSON message contains the definition of the service parameters that are provided by the underlying technical service with their default values, if available. The user can then specify values for these parameters in the modal window.

A **configuration response** is sent from the external parameter configuration tool to CT-MG as soon as the configuration is successfully finished or canceled:

- If the configuration is successfully finished, the JSON message contains the specified parameter values which are instantly validated by CT-MG.
 - If the validation is successful, the parameter data is stored in CT-MG and the modal window is closed. If the validation fails, a corresponding validation error is displayed in the inline frame element and a new configuration request is sent.
- If the configuration is canceled, the modal window is closed.

Message Syntax

The syntax of the messages must be as shown in the following examples.

Initialization message:

Configuration request:

```
{"messageType":"CONFIG_REQUEST",
    "locale":en",
    "parameters":[
        {"id":"par1", "valueType":"INTEGER", "value":"", ...},
        {"id":"par2", "valueType":"BOOLEAN", "value":"true", ...},
        {...}
        ]
}
```

Configuration response - configuration process finished:

Configuration response - configuration process canceled:

Parameter Definitions

The parameters that are to be configured with an external parameter configuration tool are defined in the technical services in CT-MG. For details on technical services, refer to the *Technology Provider's Guide*.

The parameter definitions must be passed from CT-MG to the external tool and vice versa. Refer to the next section for the complete set of parameter definitions.

Parameter Syntax

In configuration requests and responses, the syntax for the parameters with the different data types must be as shown in the following examples.

Parameters of type BOOLEAN:

Parameters of type INTEGER:

Parameters of type LONG:

```
an outgoing Web service of the createUsers call will
be executed",
   "value":"0",
   "readonly":false,
   "modificationType":"STANDARD",
   "valueError":false,
},
{...}]
```

Parameters of type STRING:

Parameters of type ENUMERATION:

```
{"messageType":"CONFIG REQUEST",
    "locale":en",
    "parameters":[
        {"id":"DISK_SPACE",
         "valueType": "ENUMERATION",
         "mandatory":false,
         "description": "Incremental disk storage",
         "value":"1",
         "readonly": false,
         "modificationType": "STANDARD",
         "valueError": false,
         "options":[
{"id":"1",
             "description": "Minimum Storage (100 GB)"
             {"id":"2",
             "description": "Optimum Storage (200 GB)"
             {"id":"3",
             "description": "Maximum Storage (300 GB)"
        },
{...}]
```

Parameters of type DURATION:

```
{"messageType":"CONFIG_REQUEST",
    "locale":en",
    "parameters":[
        {"id":"PERIOD",
        "valueType":"DURATION",
```

```
"minValue":"0",
    "maxValue":"106751991167",
    "mandatory":false,
    "description":"Number of days after which the
    subscription is deactivated",
    "value":"",
    "readonly":false,
    "modificationType":"STANDARD",
    "valueError":false,
    },
    {...}]
```

5.3 Overview of Tasks

To enable the integration with CT-MG, the following development tasks have to be implemented on the side of the external parameter configuration tool. CT-MG provides resources that support you in the implementation.

Implementing Cross-Document Messaging

For sending text messages from the domain of the external parameter configuration tool to the domain of CT-MG, you can use the public JavaScript API for cross-document messaging.

CT-MG provides a sample tool implemented in JavaScript. You can integrate it with CT-MG to see how cross-document messaging works. The sample demonstrates the key aspects involved in the integration.

The sample tool is provided in the CT-MG integration package

(fujitsu-bss-integration-pack.zip). From the readme.htm file of the integration package, you can download the sample and directly access the description on how to integrate it.

Implementing JSON Encoding and Decoding

For sending data to CT-MG, the parameter configuration tool must encode its text messages to JSON. JSON messages received from CT-MG must be decoded.

If you want to encode and decode the text messages with JavaScript, you can use the public domain JavaScript library <code>json2.js</code>. It contains the methods required for implementing JSON encoders and decoders.

Implementing the Data Structures

For the exchange of data, the message and parameter definitions must be implemented in accordance with the predefined syntax. For details, refer to *Data Exchange* on page 33.

A JavaScript library, <code>configurationAPI.js</code>, is provided that you can use for implementing the message and parameter definitions. The library is included in the CT-MG integration package (fujitsu-bss-integration-pack.zip). From the <code>readme.htm</code> file of the integration package, you can directly access the library.

Next Steps

To link the external parameter configuration tool with CT-MG, the supplier has to specify the URL of the tool in the service definition. The URL is not validated by CT-MG, neither for syntax nor for semantic. The supplier has to ensure that the script does not introduce any security leaks. For details, refer to the *Supplier's Guide*.

6 Integrating Certificates for Trusted Communication

Certificates are required for CT-MG to allow for trusted communication between CT-MG and an application underlying a technical service, a payment service provider (PSP), an Identity Provider (IdP) or a Security Token Service (STS).

The following organizations are involved when using certificates:

- Platform operator
- Technology providers integrating their applications with CT-MG.
- PSPs whose services are to be integrated with CT-MG for invoicing and payment collection.
- · Organizations integrating an external process control system.
- Any other organization using Web service calls to or from CT-MG

6.1 Introduction

Web service calls coming from CT-MG (e.g. for provisioning application instances for services, or for integrating a process control system) or sent to it (e.g. by an application such as a PSP system) can be secured with SSL. SSL is used for authentication and for encryption at the transport level.

Every HTTPS connection involves a client and a server. Depending on the calling direction, CT-MG can act as a server (Web service calls to CT-MG) or as a client (Web service calls from CT-MG).

Every application integrated with CT-MG or accessing the platform services acts as a Web service client. CT-MG acts as the server, and the client must provide its authenticating data to the server. Three options are available:

Basic authentication:

The caller sends the key and password of a CT-MG user and addresses the CT-MG Web services with the BASIC suffix. This mechanism does not apply certificates for user authentication. However, certificates are involved because the communication between the client and CT-MG must be secured using TLS/SSL and HTTPS. You should also configure your network's firewall to block JNDI lookups from the outside when using basic authentication. Basic authentication must be used for calling CT-MG functions that require the specification of a user role. The user role determines whether the user is allowed to execute the function. Basic authentication can only be used if CT-MG is installed in INTERNAL authentication mode.

Certificate-based authentication:

The caller provides a certificate to the CT-MG server. It addresses the CT-MG Web services with the CLIENTCERT suffix. In this case, the following requirements must be fulfilled:

- The distinguished name (DN) of the client's certificate must correspond to the distinguished name (DN) configured and stored in CT-MG for the corresponding organization.
- CT-MG must trust the client's certificate: The CT-MG truststore must contain a certificate with a valid signing chain to the certificate presented by the client.

Certificate-based authentication must be used when integrating a PSP such as Heidelpay. Web services calling PSP-related functions of CT-MG do not require the specification of a user role.

Certificate-based authentication can be used in both authentication modes (INTERNAL and SAML_SP). Refer to *Integrating Certificates for Trusted Communication* on page 38 for details.

· Security token service authentication:

The caller addresses the CT-MG Web services with the STS suffix.

Web service calls are authenticated by means of a security token service (STS). This is a Web service that issues security tokens as defined in the WS-Security/WS-Trust specification. WS-Security (Web Services Security) is an extension to SOAP to apply security to Web services.

This mechanism does not apply certificates for user authentication. However, certificates are involved because the communication between the client and CT-MG must be secured using TLS/SSL and HTTPS.

Security token service authentication can only be used if CT-MG is installed in SAML_SP authentication mode.

Note: Both, the server and the client certificates must be created and signed using the same JRE/JDK. Otherwise, the communication may fail.

Terminology

CT-MG uses an **X.509** certificate to prove the identity of an entity. This certificate is always used to prove the server's identity and optionally to prove the client's identity.

A certificate has a **subject** which usually identifies the owner of the certificate, and an **issuer** who signed the certificate. A certificate also includes a validity period. Cryptographic algorithms ensure that the information contained in the certificate cannot be changed without breaking the signature of the certificate.

The subject as well as the issuer is given as a **distinguished name (DN)** consisting of a list of key-value pairs. One of the standardized keys is called **common name (CN)**. The CN is of particular importance to HTTPS servers: The CN must contain the server's domain; otherwise the client will refuse the connection.

The process of issuing a certificate for another entity is called **signing**. Certificates always form a chain up to a certain **root certificate**. In a root certificate, the subject and the issuer are one and the same entity. Such certificates are called **"self-signed"**.

Signing certificates or proofing that someone is the owner of a certificate requires the possession of the corresponding **private key**. While certificates can be distributed to other parties, special care must be taken to keep the private key secret.

Each client and server may have a keystore and a truststore. A **keystore** is used to keep certificates along with the corresponding private key. This means that a keystore is used to prove your own identity or to sign certificates. A **truststore** contains public certificates of other entities.

6.2 Requirements for Web Service Calls from CT-MG

For the provisioning of application instances and for integrating external process control or PSP systems, CT-MG calls other Web services which can be addressed by HTTPS. In this scenario, CT-MG is the Web service client while the other entity is the HTTPS server. The following requirements must be fulfilled to establish a connection to the server:

• The server must present a valid certificate: The CN (common name) must correspond to the server's domain name and it must be valid at the time of calling.

 The client (CT-MG) must trust the server's certificate. To this end, the server's certificate must have been imported into the client's truststore, or the client's truststore must contain a root certificate with a valid signing chain to the certificate presented by the server.


6.3 Requirements for Web Service Calls to CT-MG

CT-MG provides Web services (platform services) that can be called by other systems, such as an external process control or a PSP system. In this scenario, CT-MG is the HTTPS server while the other system is a Web service client. The following requirements must be met to establish a connection to CT-MG:

- The CT-MG server must present a valid certificate: The CN (common name) must correspond
 to the server's domain name and it must be valid at the time of calling.
- The clients must trust the CT-MG server certificate for SSL connections: The clients' truststore must contain the CT-MG server certificate.
- In case of certificate-based authentication, CT-MG must trust the client's certificate: The CT-MG truststore must contain a certificate with a valid signing chain to the certificate presented by the client.

6.4 Certificate Integration Procedures

The following figure illustrates the process and tasks involved in using custom root certificates for secure communication:



As a developer who integrates an application or external system with CT-MG and wants to make use of certificates, you need to perform the tasks depicted in gray. These tasks are described in detail in the subsequent sections. The operator tasks are described in the *Operator's Guide*.

6.4.1 Creating a Certificate and a Signing Request

The following command creates a certificate:

```
%JAVA_HOME%\bin\keytool -genkey -alias tpcert -keysize 1024 -keystore keystore.jks
```

You will be prompted for a password for the keystore.jks keystore that will be created containing the certificate identified by the alias tpcert. In addition, you need to specify detailed information on your organization and its location.

Create a certificate signing request (CSR) by executing the following command:

```
%JAVA_HOME%\bin\keytool -certreq -alias tpcert -file tpcert.csr -keystore keystore.jks
```

The alias tpcert refers to the created certificate. The result of the above command is a file name tpcert.csr. Send this file to the certification authority (CA), for example, the operator.

6.4.2 Importing the Signed Certificates

When the signing process is completed, you will receive the following from the operator:

- CA public (root) certificate for CT-MG
- · Self-signed domain certificate
- · Your own, signed certificate

You have to import the certificates into your application server's keystore and truststore as follows:

1. Import the CA public certificate into the client's keystore by executing the following command:

```
%JAVA_HOME%\bin\keytool -import -alias cacert -file ca.crt -keystore keystore.jks
```

2. Update your certificate (signed by the operator) in the keystore so that the certificate chain will be stored in the keystore:

```
%JAVA_HOME%\bin\keytool -import -file <bssDomain> -keystore cacerts.jks -alias bssDomain
```

For checking which entries are contained in your keystore, you can execute the following command:

```
%JAVA_HOME%\bin\keytool -list -keystore keystore.jks
```

The result should look like

```
Keystore type: jks
Keystore provider: SUN

Your keystore contains two entries.

tpcert, 2010-05-21, keyEntry,
Certificate finger print (MD5):
   FA:E7:AF:99:33:A5:C9:8E:4F:28:50:04:08:0F:3F:4A
mykey, 2010-05-21, trustedCertEntry,
Certificate finger print (MD5):
   33:E5:B9:77:C3:34:8R:9F:34:99:1G:78:D5:3H:4B:22
```

3. Import the domain certificate into the client's truststore by executing the following command:

```
%JAVA_HOME%\bin\keytool -import -file <bssDomain>
-keystore cacerts.jks -alias bssDomain
```

6.4.3 Importing the CT-MG Server Certificate

To secure the calls from CT-MG to the provisioning service of an application, the CT-MG server certificate has to be imported into the truststore valid for the provisioning service so that the service can identify CT-MG as a client.

Execute the following command:

%JAVA_HOME%\bin\keytool -import -file bsssrv.crt -keystore keystore.jks -alias bsssrv

Appendix A: Customer Billing Data

The charges for the usage of a service in CT-MG are calculated based on the price model defined for the service, customer, or subscription.

A supplier or reseller can export the billing data for one or several of his customers for a specific time. Suppliers also have access to the billing data of customers of broker organizations that sell their services. The exported data can be forwarded, for example, to an accounting system for further processing.

The result of the export is stored in an XML file, the customer billing data file. The billing data file conforms to the XML schema BillingResult.xsd, which can be found in the CT-MG integration package.

The billing data file is named <date>BillingData.xml, where <date> represents the creation date.

This appendix describes the meaning of the elements and attributes that may occur in a billing data file.

BillingDetails

Top-level container element of a billing data file. For each subscription, a BillingDetails element is added to the billing data file.

A ${\tt BillingDetails}$ element contains the following subelements:

- Period (see Period on page 44)
- OrganizationDetails (see OrganizationDetails on page 45)
- Subscriptions (see Subscriptions on page 45)
- OverallCosts (see OverallCosts on page 58)

A BillingDetails element has the following attributes:

key - (optional, data type long) Unique identifier allowing, for example, accounting systems to relate billing data to an invoice. The billing data key is printed on the invoice. Suppliers and customers may use the billing data key to create a detailed billing report for an existing invoice or subscription. A supplier can retrieve the key from a billing report, a customer gets the billing data key from the corresponding invoice.

timezone - (required, data type string) Time zone based on the UTC time standard. It reflects the standard server time without daylight saving time. For example, 18:00:00 o'clock on June 1st in Berlin (UTC+1) will be output as follows in the XML file:

The time zone is relevant for price models with costs (see *PriceModel* on page 46).

Period

Specifies the billing period for which the data is exported. The start and end time of the billing period are output according to the start day of the billing period which was defined by the supplier or reseller.

A Period element has the following attributes:

• startDate - (data type long) Start time of the period. The start time is specified in milliseconds, the starting point for the calculation is 1970-01-01, 00:00.

- startDateIsoFormat (optional, data type dateTime) Same as startDate, but specified in ISO 8601 format (YYYY-MM-DDThh:mm:ss.fffz).
- endDate (data type long) End time of the period. The end time is specified in milliseconds, the starting point for the calculation is 1970-01-01, 00:00.
- endDateIsoFormat (optional, data type dateTime) Same as endDate, but specified in ISO 8601 format (YYYY-MM-DDThh:mm:ss.fffZ).

Example:

```
<Period startDateIsoFormat="2012-08-31T22:00:00.000Z"
    startDate="1346450400000"
    endDateIsoFormat="2012-09-30T22:00:00.000Z"
    endDate="1349042400000"/>
```

OrganizationDetails

Provides details of the customer for which the billing data have been exported. The details may include a Udas element with custom attributes that store additional information on the customer organization.

An OrganizationDetails element contains the following subelements:

Email

Specifies the email address of the organization (data type string).

Name

Specifies the name of the organization (data type string).

Address

Specifies the address of the organization (data type string).

Paymenttype

Specifies the payment type used for subscriptions of the organization (data type string).

Example:

Subscriptions

Contains the billing data for the subscriptions of the customer which are relevant for the current billing period.

For every subscription of an organization, the <code>Subscriptions</code> element contains a <code>Subscription</code> element. In this element, the costs of the affected subscription are specified. A <code>Subscription</code> element also contains the billing data for the price model of the subscription in the <code>PriceModel</code> element. A <code>Udas</code> element with custom attributes that store additional information on the subscription may also be included.

A Subscription element has the following attributes:

- id (required, data type string) Unique subscription name.
- purchaseOrderNumber (data type string) Optional reference number as specified by the customer when subscribing to a service.

Example:

Udas

Contains custom attributes that store additional information on an organization or subscription. This could be, for example, the profit center to which a customer's revenue is to be accounted.

A Udas element may be included in an OrganizationDetails or a Subscription element.

For every custom attribute, a Uda element is included in the Udas element.

A Uda element has the following attributes:

- id (required, data type string) ID of the custom attribute.
- value (required, data type string) Value of the custom attribute.

Example:

PriceModel

Contains the billing data for a price model used to calculate the utilization charges for a subscription.

A PriceModel element is included in every subscription element. It contains the following subelements:

- UsagePeriod (see UsagePeriod on page 47)
- GatheredEvents (see GatheredEvents on page 47)

- PeriodFee (see PeriodFee on page 49)
- UserAssignmentCosts (see UserAssignmentCosts on page 49)
- OneTimeFee (see OneTimeFee on page 51)
- PriceModelCosts (see PriceModelCosts on page 51)
- Parameters (see Parameters on page 52)

A PriceModel element has the following attributes:

id - (required, data type string) Unique name identifying the price model.

calculationMode - (required, data type string) Cost calculation option of the price model. Can be set to one of the following values: FREE_OF_CHARGE (the service is free of charge), PRO_RATA (the costs are calculated exactly for the time a service is used, based on milliseconds), PER_UNIT (the costs are calculated based on fixed time units).

UsagePeriod

Specifies the actual period in which a price model is used for calculating the charges of a subscription.

A usage period usually begins when a customer subscribes to a service and ends when the subscription is terminated. In case a free trial period is defined for the service, the usage period begins when the free trial period has ended. When the customer upgrades or downgrades the subscription, a new usage period is started in which the price model of the new service is applied. If the customer changes elements that determine how the charges for the service are calculated (e.g. the number of assigned users, the service roles of the assigned users, or the parameter values), a new usage period is started in which the updated elements are applied.

A UsagePeriod element is contained in a PriceModel element.

A UsagePeriod element has the following attributes:

- startDate (data type long) Start time of the period. The start time is specified in milliseconds, the starting point for the calculation is 1970-01-01, 00:00.
- startDateIsoFormat (optional, data type dateTime) Same as startDate, but specified in ISO 8601 format (YYYY-MM-DDThh:mm:ss.fffZ).
- endDate (data type long) End time of the period. The end time is specified in milliseconds, the starting point for the calculation is 1970-01-01, 00:00.
- endDateIsoFormat (optional, data type dateTime) Same as endDate, but specified in ISO 8601 format (YYYY-MM-DDThh:mm:ss.fffZ).

Example:

GatheredEvents

Specifies the costs for all chargeable events that occurred in the current usage period of the subscription. These include, for example, login and logout by users to the underlying application, the completion of specific transactions, or the creation or deletion of specific data. It depends on the implementation and integration of the underlying application which events are available.

A GatheredEvents element is contained in a PriceModel element.

A GatheredEvents element contains the following subelements:

- Event
- GatheredEventsCosts

Event

For every event, an Event element is included in the GatheredEvents element.

An Event element has the following attribute:

id - (required, data type string) Event ID as specified in the technical service definition.

An Event element contains the following subelements:

- Description
- SingleCost
- NumberOfOccurence
- CostForEventType

Description

Contains the description of the event.

SingleCost

Specifies the price for the event as defined in the price model. If an event has stepped prices, this element is omitted. A SteppedPrices element is included instead (see *SteppedPrices* on page 57).

A singleCost element has the following attribute:

amount - (required, data type decimal) Price for a single event.

NumberOfOccurence

Specifies how often the event occurred.

A NumberOfOccurence element has the following attribute:

amount - (required, data type long) Number of times the event occurred.

CostForEventType

Specifies the total costs for the event in the billing period.

A CostForEventType element has the following attribute:

amount - (required, data type decimal) Total costs for the event. The total costs for an event are calculated from the singular costs (SingleCost) multiplied with the number of occurrences (NumberOfOccurence). If role-based costs and/or stepped prices are specified for events, these costs are added (see *RoleCosts* on page 56 and *SteppedPrices* on page 57). The value is rounded to two decimal places.

GatheredEventsCosts

Specifies the total costs for all events in the current GatheredEvents element.

A GatheredEventsCosts element has the following attribute:

amount - (required, data type decimal) Total costs for events. The value is rounded to two decimal places.

Example:

PeriodFee

Specifies the costs for using the subscription in the given usage period.

For each subscription, a charge can be defined that a customer has to pay on a recurring basis. Monthly, weekly, daily, or hourly periods are supported. The recurring charge for a subscription is independent of the amount of users, events, or other usage data.

The calculation of the charges depends on the cost calculation option which was chosen for the price model (see *PriceModel* on page 46 for details).

A PeriodFee element is contained in a PriceModel element.

A PeriodFee element has the following attributes:

- basePeriod (required, data type string) Period on which the charges are based. Can be set to one of the following values: MONTH, WEEK, DAY, HOUR.
- basePrice (required, data type decimal) Recurring charge per base period according to the
 price model.
- factor (required, data type decimal) Factor used to calculate the period fee for the subscription. The factor is calculated from the usage period of the subscription divided by the base period (basePeriod). The recurring charge is multiplied with this factor to calculate the total costs (price).
- price (required, data type decimal) Total period fee for the subscription. This value is calculated from the recurring charge (basePrice) multiplied with the factor (factor). The value is rounded to two decimal places.

Example:

UserAssignmentCosts

Specifies the costs for the user assignments to the subscription.

For the users assigned to a subscription, a charge can be defined that a customer has to pay on a recurring basis. Monthly, weekly, daily, or hourly periods are supported. The charge depends on the amount of time units one or more users are assigned to the subscription. This type of charge can only be defined for services with the login or user access type.

The recurring charge for users is independent of the recurring charge per subscription or other usage data.

For this type of charge, stepped prices can be applied: Recurring charges can be defined that depend on the sum of the time units of all user assignments.

The calculation of the charges depends on the cost calculation option which was chosen for the price model (see *PriceModel* on page 46 for details).

With per time unit calculation, the costs for a time unit in which a user is assigned to a subscription are always fully charged. There is no difference in the costs between a user who is assigned from the start until the end of the time unit and a user who is assigned for a part of the time unit only. A time unit is charged only once if a user is deassigned from and re-assigned to a subscription within the same time unit. Yet, canceling an assignment, deleting the user, and then creating a new user with the same user ID is treated as if two different users are assigned to the subscription. The time unit is charged twice, accordingly.

A UserAssignmentCosts element is contained in a PriceModel element.

A UserAssignmentCosts element has the following attributes:

- basePeriod (optional, data type string) Period on which the charges are based. Can be set to one of the following values: MONTH, WEEK, DAY, HOUR.
- basePrice (optional, data type decimal) Recurring charge for users per base period according to the price model. If the charge for users has stepped prices, this attribute is omitted.
- factor (optional, data type decimal) Factor used to calculate the costs for the user assignments. The factor is calculated by summing up the factors for each user specified in the UserAssignmentCostsByUser element. The recurring charge (basePrice) is multiplied with this factor to calculate the costs (price).
- numberofusersTotal (optional, data type long) Number of users assigned to the subscription in the usage period.
- total (data type decimal) Total costs for the user assignments including role-based costs and stepped prices. The value is rounded to two decimal places. For details on role-based costs and stepped prices, refer to *RoleCosts* on page 56 and *SteppedPrices* on page 57.
- price (optional, data type decimal) Costs for the user assignments. This value is calculated from the recurring charge (basePrice) multiplied with the factor (factor). The value is rounded to two decimal places.

A UserAssignmentCosts element contains the following subelement. If role-based costs and/or stepped prices are specified, a RoleCosts element and/or SteppedPrices element is also present (see *RoleCosts* on page 56 and *SteppedPrices* on page 57).

UserAssignmentCostsByUser

Specifies the fraction of the usage period a user was assigned to the subscription.

A UserAssignmentCostsByUser element has the following attributes:

- factor (required, data type decimal) Fraction of the usage period the given user was assigned to the subscription. The factors of the single user assignments are summed up to calculate the total costs for the user assignments.
- userId (required, data type string) User ID.

Example:

OneTimeFee

Specifies the one-time fee for the subscription.

A one-time fee defines the amount a customer has to pay for a subscription in the first billing period of the subscription. It is added to the total charges for the first billing period. It is independent of the number of users, events, or other usage data.

If a one-time fee is defined for a service to which a customer upgrades or downgrades a subscription, it is added to the total charges for the customer, even if the service from which the customer migrates also defines a one-time fee.

A OneTimeFee element is contained in a PriceModel element.

A OneTimeFee element has the following attributes:

- amount (required, data type decimal) Total costs for the one-time fee. The value is rounded to two decimal places.
- baseAmount (required, data type decimal) One-time fee as defined in the price model.
- factor (required, data type long) Factor used for calculating the one-time fee. Since this charge occurs only once, the factor is 1 for the first billing period, and 0 in case the one-time fee has already been charged in a previous billing period.

Example:

PriceModelCosts

Specifies the total costs for the subscription in the current usage period.

A PriceModelCosts element is contained in a PriceModel element.

A PriceModelCosts element has the following attributes:

- currency (required, data type string) ISO code of the currency in which the costs are calculated.
- amount (required, data type decimal) Total amount of the costs for the subscription. The
 value is rounded to two decimal places.

Example:

Parameters

Specifies the costs for parameters defined for the service underlying the subscription.

A price model can define prices for service parameters and options. It depends on the implementation and integration of the underlying application whether and which parameters and options are available.

A price can be defined for every parameter and option, and the price can be charged per subscription or per user assigned to the subscription. Numeric parameters are a multiplier for the price. For boolean parameters, the multiplier is 1 if the value is true. In all other cases, the multiplier is 0.

The calculation of charges for parameters and options depends on the cost calculation option which was chosen for the price model (see *PriceModel* on page 46 for details).

If the charges for a subscription are calculated per time unit and a customer changes a parameter value within a time unit, the affected time unit is charged pro rata. This means that the customer is charged exactly for the time each parameter value is set.

For numeric parameters, stepped prices can be applied per subscription: Different prices can be defined depending on the parameter values.

The prices for parameters and options are independent of other price model elements.

A Parameters element is contained in a PriceModel element.

A Parameters element contains the following subelements:

- Parameter
- ParametersCosts

Parameter

For every parameter, a Parameter element is included in the Parameters element.

A Parameter element has the following attribute:

id - (required, data type string) Parameter ID.

A Parameter element contains the following subelements:

- ParameterUsagePeriod
- ParameterValue
- PeriodFee
- UserAssignmentCosts
- ParameterCosts
- Options

ParameterUsagePeriod

Specifies the actual usage period for the parameter.

The usage period for a parameter begins when a customer subscribes to the service with the given parameter definition in the price model and ends when the subscription is terminated.

In case a free trial period is defined for the service, the usage period for the subscription begins when the free trial period has ended. If a parameter value is changed, a new usage period is started in which the updated value is applied for calculating the costs.

A ParameterUsagePeriod element has the following attributes:

• startDate - (data type long) Start time of the period. The start time is specified in milliseconds, the starting point for the calculation is 1970-01-01, 00:00.

- startDateIsoFormat (Optional, data type dateTime) Same as startDate, but specified in ISO 8601 format (YYYY-MM-DDThh:mm:ss.fffz).
- endDate (data type long) End time of the period. The end time is specified in milliseconds, the starting point for the calculation is 1970-01-01, 00:00.
- endDateIsoFormat (optional, data type dateTime) Same as endDate, but specified in ISO 8601 format (YYYY-MM-DDThh:mm:ss.fffZ).

ParameterValue

Specifies the costs and data type for the parameter.

A ParameterValue element has the following attributes:

- amount (required, data type string) Costs for the parameter as defined in the price model.
- type (required, data type string) Data type of the parameter. Can be set to one of the following values: BOOLEAN, INTEGER, LONG, STRING, ENUMERATION, DURATION.

PeriodFee

Specifies the costs for using the parameter in the given usage period. If a parameter has stepped prices, a SteppedPrices element is included in the PeriodFee element.

A PeriodFee element has the following attributes:

- basePeriod (required, data type string) Period on which the charges are based. Can be set to one of the following values: MONTH, WEEK, DAY, HOUR.
- basePrice (optional, data type decimal) Recurring charge per base period according to the price model. If a parameter has stepped prices, this attribute is omitted.
- factor (required, data type decimal) Factor used to calculate the costs for using the parameter. The factor is calculated from the usage period divided by the base period (basePeriod). The recurring charge (basePrice) is multiplied with this factor to calculate the costs (price).
- price (required, data type decimal) Costs for using the parameter. This value is calculated from the recurring charge (basePrice) multiplied with the factors (factor and valueFactor). The value is rounded to two decimal places.
- valueFactor (required, data type float) Factor to calculate the total costs for using the parameter depending on the parameter value. The recurring charge (basePrice) is multiplied with this factor to calculate the costs (price). This factor is set depending on the data type of the parameter. For numeric parameters it is set to the value of the parameter. For boolean parameters, the factor is set to 1 if the value is true. In all other cases, the factor is set to 0.

UserAssignmentCosts

Specifies the costs for the parameter related to the user assignments of the subscription based on the price per user for the parameter as defined in the price model. If costs for service roles are defined, a RoleCosts element is included in the UserAssignmentCosts element (see *RoleCosts* on page 56 for details).

A UserAssignmentCosts element has the following attributes:

- basePeriod (required, data type string) Period on which the charges are based. Can be set to one of the following values: MONTH, WEEK, DAY, HOUR.
- basePrice (required, data type decimal) Recurring charge for users per base period for the parameter according to the price model.
- factor (required, data type decimal) Factor used to calculate the costs for using the parameter. The factor is calculated from the parameter usage period divided by the base

period (basePeriod) multiplied with the number of users. The recurring charge (basePrice) is multiplied with this factor to calculate the costs (price).

- price (required, data type decimal) Costs for using the parameter. This value is calculated from the recurring charge (basePrice) multiplied with the factors (factor and valueFactor). The value is rounded to two decimal places. If stepped prices are defined for user assignments, the costs are given in the price attribute.
- total (data type decimal) Total costs for using the parameter including role-based costs. The value is rounded to two decimal places. For details on role-based costs, refer to *RoleCosts* on page 56.
- valueFactor (required, data type float) Factor to calculate the total costs for using the parameter depending on the parameter value. The recurring charge (basePrice) is multiplied with this factor to calculate the costs (price). This factor is set depending on the data type of the parameter. For numeric parameters it is set to the value of the parameter. For boolean parameters, the factor is set to 1 if the value is true. In all other cases, the factor is set to 0.

ParameterCosts

Specifies the total costs for using the parameter.

A ParameterCosts element has the following attribute:

amount - (required, data type decimal) Total costs for the parameter calculated by summing up the costs specified in the PeriodFee and the UserAssignmentCosts element for the parameter and its options. If role-based costs and/or stepped prices are specified for the parameter, these are added (see *RoleCosts* on page 56 and *SteppedPrices* on page 57). The value is rounded to two decimal places.

ParametersCosts

Specifies the total costs for all parameters.

A ParametersCosts element has the following attribute:

amount - (required, data type decimal) Total costs for the parameters calculated by summing up the costs of the individual parameters as specified in the ParameterCosts elements. The value is rounded to two decimal places.

Example:

```
<Parameters>
 <Parameter id="MAX FOLDER NUMBER2">
   <ParameterUsagePeriod endDate="1306879200000"</pre>
    endDateIsoFormat="2011-05-31T22:00:00.000Z"
    startDate="1304755088065"
    startDateIsoFormat="2011-05-07T07:58:08.065Z"/>
   <ParameterValue amount="200" type="INTEGER"/>
   <PeriodFee basePeriod="MONTH" basePrice="0.00"</pre>
    factor="0.5337789669205496" price="0.00" valueFactor="200.0"/>
   <UserAssignmentCosts basePeriod="MONTH" basePrice="0.00"</pre>
    factor="0.5337726052867383" total ="0.00"
    price="0.00" valueFactor="200.0"/>
    <ParameterCosts amount="0.00"/>
 </Parameter>
 <ParametersCosts amount="600.00"/>
</Parameters>
```

Options

Specifies the costs for parameter options.

An Options element is contained in a Parameter element.

For every option, an Option element is included in the Options element.

An Option element has the following attribute:

id - (required, data type string) Option ID.

An option element contains the following subelements:

- PeriodFee
- UserAssignmentCosts
- OptionCosts

PeriodFee

Specifies the costs for using the parameter option in the given usage period.

A PeriodFee element has the following attributes:

- basePeriod (required, data type string) Period on which the charges are based. Can be set to one of the following values: MONTH, WEEK, DAY, HOUR.
- basePrice (required, data type decimal) Recurring charge per base period according to the price model.
- factor (required, data type decimal) Factor used to calculate the costs for using the parameter option. The factor is calculated from the usage period divided by the base period (basePeriod). The recurring charge (basePrice) is multiplied with this factor to calculate the total costs (price).
- price (required, data type decimal) Costs for the parameter option. This value is calculated from the recurring charge (basePrice) multiplied with the factor (factor), and is rounded to two decimal places.

UserAssignmentCosts

Specifies the costs for the parameter option related to the user assignments of the subscription based on the price per user for the option as defined in the price model. If costs for service roles are defined, a RoleCosts element is included in the UserAssignmentCosts element (see RoleCosts on page 56).

A UserAssignmentCosts element has the following attributes:

- basePeriod (required, data type string) Period on which the charges are based. Can be set to one of the following values: MONTH, WEEK, DAY, HOUR.
- basePrice (required, data type decimal) Recurring charge for users per base period for the parameter option according to the price model.
- factor (required, data type decimal) Factor used to calculate the costs for using the parameter option. The factor is calculated from the usage period divided by the base period (basePeriod). The recurring charge (basePrice) is multiplied with this factor to calculate the costs (price).
- total (data type decimal) Total costs for using the parameter option including role-based costs. The value is rounded to two decimal places. For details on role-based costs, refer to *RoleCosts* on page 56.
- price (required, data type decimal) Costs for using the parameter option. This value is calculated from the recurring charge (basePrice) multiplied with the factor (factor). The value is rounded to two decimal places. If stepped prices are defined for user assignments, the costs are given in the price attribute.

OptionCosts

Specifies the total costs for using the parameter option.

An OptionCosts element has the following attribute:

amount - (required, data type decimal) Total costs for the parameter option calculated by summing up the costs specified in the PeriodFee and the UserAssignmentCosts element. The value is rounded to two decimal places.

Example:

RoleCosts

Specifies the costs for service roles.

If defined for the underlying application, roles can be used to grant specific privileges to different users. The roles are specified in the technical service definition as service roles. Service roles can be mapped to corresponding permissions in the application.

For each role, a price can be defined. This price is added to the base price per user in the cost calculation for a billing period.

The calculation of the charges for service roles depends on the cost calculation option which was chosen for the price model (see *PriceModel* on page 46 for details).

If the charges are calculated per time unit and the role assignment of a user is changed within a time unit, the affected time unit is charged pro rata. This means that the customer is charged exactly for the time each user role is assigned.

If the charges are calculated per time unit and a user with a specific role is removed from the subscription and assigned to it again with a different role in the same time unit, the customer is also charged for the time during which the user is not assigned to the subscription. This means that he is charged with the price for the first service role until the user is assigned to the subscription with the second service role.

A RoleCosts element is contained in a UserAssignmentCosts element (as subelement of the PriceModel, Parameters, Or Option element).

A RoleCosts element has the following attribute:

total - (required, data type decimal) Total amount of costs for the service roles. The value is rounded to two decimal places.

For every service role, a RoleCost element is included in the RoleCosts element.

A RoleCost element has the following attributes:

• id - (required, data type string) ID of the service role.

- basePrice (required, data type decimal) Recurring charge for the service role according to the price model.
- factor (required, data type decimal) Factor used to calculate the costs for the service role. The factor is calculated as a fraction of the actual usage period. The recurring charge (basePrice) is multiplied with this factor to calculate the costs (price).
- price (required, data type decimal) Costs for the service role. This value is calculated from the recurring charge (basePrice) multiplied with the factor (factor). The value is rounded to two decimal places.

Example:

SteppedPrices

Specifies the stepped prices for a user assignment, event, or parameter.

Stepped prices allow for the definition of ranges for which different price factors apply. Step limits, i.e. the upper limits of ranges, can be set for:

- The **sum of the time units** users are assigned and work with a subscription in a billing period. For example, up to 10 hours one user is assigned to a subscription cost 10.00 € per hour, every additional hour the user is assigned costs 8.00 €.
- The **number of events** occurring in the usage of a subscription. For example, up to 10 file downloads cost 1.00 € per download, any additional download costs 0.50 €.
- Values of numeric parameters. For example, uploading up to 100 files costs 1.00 € per file, any additional upload costs 0.50 € per file.

Stepped prices are independent of any other price model elements.

A SteppedPrices element is contained in UserAssignmentCosts (as subelement of the PriceModel element), Event, and PeriodFee (as subelement of the Parameters element) elements.

A SteppedPrices element has the following attribute:

amount - (required, data type decimal) Summed up costs for all steps including the last one.

For every price step, a SteppedPrice element is included in a SteppedPrices element.

A SteppedPrice element has the following attributes:

- additionalPrice (required, data type decimal) Summed up costs for the previous steps. The costs are calculated from the limit, freeAmount and basePrice attributes of the previous step ((limit freeAmount) * price). The additionalPrice attribute of the first step always has a value of 0. The value is rounded to two decimal places.
- basePrice (required, data type decimal) Costs for the current step according to the price model.
- freeAmount (required, data type long) Amount of units for the current step that are considered as a fixed discount, for example, the number of users that are free of charge. The

value corresponds to the value of the limit attribute in the previous step. The freeAmount attribute of the first step always has a value of 0.

- limit (required, data type string) Step limit as defined in the price model.
- stepAmount (optional, data type decimal) Summed up costs for the current step. These costs are calculated from the basePrice and stepEntityCount attributes of the current step. The value is rounded to two decimal places.
- stepEntityCount (optional, data type decimal) Factor used to calculate the costs for the current step.

Example:

```
<PriceModel calculationMode="PRO RATA" id="350001">
 <UserAssignmentCosts basePeriod="MONTH" factor="2.707940780619112"</pre>
numberOfUsersTotal="4" price="1283.18">
    <SteppedPrices amount="1283.18">
      <SteppedPrice additionalPrice="0.00" basePrice="500.00"</pre>
       freeAmount="0" limit="2" stepAmount="1000.00"
stepEntityCount="2"/>
      <SteppedPrice additionalPrice="1000.00" basePrice="400.00"</pre>
       freeAmount="2" limit="3" stepAmount="283.18"
       stepEntityCount="0.707940780619112"/>
      <SteppedPrice additionalPrice="1400.00" basePrice="300.00"</pre>
       freeAmount="3" limit="null" stepAmount="0.00"
stepEntityCount="0"/>
    </SteppedPrices>
  </UserAssignmentCosts>
</PriceModel>
```

OverallCosts

Contains the total amount of the charges to be paid by a customer for all subscriptions in the current billing period. The costs are given in the currency specified in the price model.

If a discount was specified, the net amount of the costs is given in the Discount element (see *Discount* on page 59). If a VAT rate was defined, it is given in the VAT element (see *VAT* on page 59).

An OverallCosts element has the following attributes:

- netAmount (required, data type decimal) Net costs after the net discount has been deducted from the original net costs (see *Discount* on page 59). The value is rounded to two decimal places.
- currency (required, data type string) ISO code of the currency in which the costs are calculated.
- grossAmount (required, data type decimal) Gross amount of the costs, calculated from the net costs (netAmount) plus VAT (see VAT on page 59). The value is rounded to two decimal places.

Example:

```
<BillingDetails key="10002" timezone="UTC+01:00">
...
<OverallCosts netAmount="900.00" currency="EUR" grossAmount="1053.00"/>
</OverallCosts>
```

```
</BillingDetails>
```

VAT

Specifies the VAT rate to be applied.

A supplier can define a basic VAT rate that applies by default to all prices for his customers. In addition to this basic VAT rate, country-specific or even customer-specific VAT rates can be defined. You can:

- Enable VAT rate support for your organization.
- Define a default VAT rate that applies to all prices for all customers.
- Define a country-specific VAT rate for every country where you want to sell your services.
- Define a customer-specific VAT rate, for example, in case a customer organization has a subsidiary located in another country than its parent organization.

The VAT rate settings have the following effects on the cost calculation for a customer:

- If VAT rate support is disabled, prices are calculated as net prices; no VAT is added to the
 overall costs.
- A customer-specific VAT rate takes priority over any default or country-specific VAT rate.
- The country-specific VAT rate for the country where the customer organization is located is applied to the cost calculation when no customer-specific VAT rate is defined.
- The default VAT rate is used in all other cases.

The VAT rate does not affect any price model elements. The calculated VAT amount is added to the overall costs and results in the gross price to be paid by a customer.

A VAT element is contained in the OverallCosts element.

A VAT element has the following attributes:

- percent (required, data type float) VAT rate in percent, specified as a decimal number.
- amount (required, data type decimal) Net amount of VAT to be added to the net costs (netAmount attribute of the OverallCosts element). The value is rounded to two decimal places.

Example:

Discount

Specifies the discount granted to the customer.

A discount can be defined for a customer which applies to all subscriptions of the customer. A discount may be valid as of the current or a future month. It can be restricted to a certain period of time. Before the time expires, the customer is notified by email so that he can react and contact the supplier.

The discount is defined as a percentage that is subtracted from the regular total price for a subscription. It is granted for all costs of a customer that incur in a billing period in which the

discount is valid. It does not matter whether the discount is valid for the whole billing period or only a part of it.

A discount is completely independent of what a customer might purchase. If a discount is changed, the new discount is valid the next time the billing data is generated. Usually, a discount is only changed in agreement with the relevant customer.

A Discount element is contained in the OverallCosts element.

A Discount element has the following attributes:

- percent (required, data type float) Percentage of costs to be deducted from the net costs, specified as a decimal number.
- discountNetAmount (required, data type decimal) Net discount to be deducted from the original net costs (netAmountBeforeDiscount). The value is rounded to two decimal places.
- netAmountAfterDiscount (required, data type decimal) Net costs after the net discount (discountNetAmount) has been deducted from the original net costs (netAmountBeforeDiscount). The value is rounded to two decimal places.
- netAmountBeforeDiscount (required, data type decimal) Net costs before the net discount (discountNetAmount) has been deducted. The value is rounded to two decimal places.

Example:

Appendix B: Revenue Share Data

In extended usage scenarios, suppliers may involve brokers and resellers in selling their services. The brokers and resellers as well as the platform operator and the owners of the marketplaces on which the services are published, usually receive a share of the revenue for the services. CT-MG calculates these revenue shares based on the billing data for the customers who use the services.

Suppliers, brokers, resellers, and marketplace owners can generate reports for their revenue shares and export the revenue share data for a specific time. Operators can export the data for all the suppliers, brokers, resellers, or marketplace owners known to their platform installation. The exported data can be forwarded, for example, to an accounting system for further processing.

The result of the export is stored in an XML file, the revenue data file. The file conforms to one of the following schemas, depending on the type of the revenue share data:

- BrokerRevenueShareResult.xsd: revenue share data for brokers
- ResellerRevenueShareResult.xsd:revenue share data for resellers
- MPOwnerRevenueShareResult.xsd: revenue share data for marketplace owners
- SupplierRevenueShareResult.xsd: revenue share data for suppliers

Each of these schemas includes the BillingBase.xsd with common definitions. All the schemas can be found in the CT-MG integration package.

The XML files containing the revenue share data are named <date>BillingData.xml, where <date> represents the creation date.

This appendix describes the meaning of the elements and attributes that may occur in the different types of revenue share data file. The first section explains elements and attributes that are common to all revenue share data files. The subsequent sections describe the individual files.

B.1 Common Elements

The sections below describe the following elements that are common to all revenue share data files:

- Period
- OrganizationData

Period

Specifies the billing period for which the data is exported. The start and end time of the billing period are output according to the start day of the billing period which was defined by the supplier or reseller.

A Period element has the following attributes:

- startDate (data type long) Start time of the period. The start time is specified in milliseconds, the starting point for the calculation is 1970-01-01, 00:00.
- startDateIsoFormat (optional, data type dateTime) Same as startDate, but specified in ISO 8601 format (YYYY-MM-DDThh:mm:ss.fffz).
- endDate (data type long) End time of the period. The end time is specified in milliseconds, the starting point for the calculation is 1970-01-01, 00:00.
- endDateIsoFormat (optional, data type dateTime) Same as endDate, but specified in ISO 8601 format (YYYY-MM-DDThh:mm:ss.fffZ).

Example:

```
<Period startDateIsoFormat="2012-08-31T22:00:00.000Z"
    startDate="1346450400000"
    endDateIsoFormat="2012-09-30T22:00:00.000Z"
    endDate="1349042400000"/>
```

OrganizationData

Provides details of an organization.

An OrganizationData element has the following attributes:

- id (required, data type string) ID of the organization.
- key (required, data type positiveInteger) Internal numeric key of the organization.

An OrganizationData element contains the following subelements:

- Email (data type string) Email address of the organization.
- Name (data type string) Name of the organization.
- Address (data type string) Address of the organization.
- CountryIsoCode (data type string) ISO code of the country where the organization is located.

Example:

```
<OrganizationData id="8e8f596c" key="37003">
  <Email>info@company.com</Email>
  <Name>Company</Name>
  <Address>Postal Address</Address>
  <CountryIsoCode>DE</CountryIsoCode>
</OrganizationData>
```

B.2 Broker Revenue Share Data

The following sections describe the XML elements and attributes that make up the revenue share data for brokers.

BrokerRevenueShareResult

Top-level container element for broker revenue share data. For each broker organization in consideration, a BrokerRevenueShareResult element is added to the billing data file.

A BrokerRevenueShareResult element has the following attributes:

- organizationId (required, data type string) ID of the broker organization.
- organizationKey (required, data type positiveInteger) Internal numeric key of the broker organization.

A BrokerRevenueShareResult element contains the following subelements:

- An OrganizationData element specifying the details of the broker organization (see *OrganizationData* on page 62).
- A Period element specifying the billing period (see *Period* on page 61).
- A Currency element for each currency for which broker revenue share data is available (see *Currency* on page 63).

Example:

```
<BrokerRevenueShareResult organizationId="cd9ffaac"
  organizationKey="19000" >
  <OrganizationData> ... </OrganizationData>
  <Period> ... </Period>
  <Currency> ... </Currency>
</BrokerRevenueShareResult>
```

Currency

Contains the broker revenue share data for a specific currency.

A currency element has the following attribute:

id - (required, data type string) ISO code of the currency.

A Currency element contains the following subelements:

- A supplier element for each supplier organization that provides a service for which the current broker organization receives a revenue share (see *Supplier* on page 63).
- A BrokerRevenue element specifying the overall revenue for the currency in its totalAmount attribute (optional, data type positive decimal, scale 2), and the overall broker revenue share for the currency in its amount attribute (required, data type positive decimal, scale 2).

Example:

Supplier

Contains the broker revenue share data for the services provided by a specific supplier.

A Supplier element contains the following subelements:

- An OrganizationData element specifying the details of the supplier organization (see *OrganizationData* on page 62).
- A Service element for each service provided by the supplier for which the current broker organization receives a revenue share (see Service on page 63).
- A BrokerRevenuePerSupplier element specifying the overall revenue for the supplier in its totalAmount attribute (optional, data type positive decimal, scale 2), and the overall broker revenue share in its amount attribute (required, data type positive decimal, scale 2).

Example:

```
<Supplier>
     <OrganizationData> ... </OrganizationData>
          <Service> ... </Service>
          <BrokerRevenuePerSupplier totalAmount="200.50" amount="20.05" />
</Supplier>
```

Service

Specifies the broker revenue share data for a specific service.

A service element has the following attributes:

• id - (required, data type string) Name of the service.

- **key** (required, data type positiveInteger) Internal numeric key of the service offered by the broker. Technically, this is a copy of the original service defined by the supplier.
- templateRey (required, data type positiveInteger) Internal numeric key of the original service defined by the supplier.

A Service element contains a ServiceRevenue element which specifies the total revenue for the service and the broker revenue share in its attributes:

- totalAmount (required, data type positive decimal, scale 2) Total revenue for the service in the billing period.
- brokerRevenueSharePercentage (required, data type positive decimal, scale 2) Percentage of the revenue the broker is entitled to.
- brokerRevenue (required, data type positive decimal, scale 2) The broker's revenue share for the service in the billing period.

A ServiceRevenue element contains a ServiceCustomerRevenue subelement for each customer who used the service. It specifies the total revenue for the service generated by the customer and the broker revenue share in its attributes:

- customerName (optional, data type string) Name of the customer organization.
- customerid (optional, data type string) ID of the customer organization.
- totalAmount (optional, data type positive decimal, scale 2) Total revenue for the service generated by the customer in the billing period.
- brokerRevenueSharePercentage (optional, data type positive decimal, scale 2) Percentage of the revenue the broker is entitled to.
- brokerRevenue (optional, data type positive decimal, scale 2) The broker's revenue share for the service generated by the customer in the billing period.

Example:

B.3 Reseller Revenue Share Data

The following sections describe the XML elements and attributes that make up the revenue share data for resellers.

ResellerRevenueShareResult

Top-level container element for reseller revenue share data. For each reseller organization in consideration, a ResellerRevenueShareResult element is added to the billing data file.

A ResellerRevenueShareResult element has the following attributes:

- organizationId (required, data type string) ID of the reseller organization.
- organizationKey (required, data type positiveInteger) Internal numeric key of the reseller organization.

A ResellerRevenueShareResult element contains the following subelements:

- An OrganizationData element specifying the details of the reseller organization (see *OrganizationData* on page 62).
- A Period element specifying the billing period (see *Period* on page 61).
- A Currency element for each currency for which reseller revenue share data is available (see *Currency* on page 65).

Example:

```
<ResellerRevenueShareResult organizationId="cd9ffaac"
  organizationKey="19000">
  <OrganizationData> ... </OrganizationData>
  <Period> ... </Period>
  <Currency> ... </Currency>
</ResellerRevenueShareResult>
```

Currency

Contains the reseller revenue share data for a specific currency.

A Currency element has the following attribute:

id - (required, data type string) ISO code of the currency.

A Currency element contains the following subelements:

- A supplier element for each supplier organization that provides a service for which the current reseller organization receives a revenue share (see *Supplier* on page 65).
- A ResellerRevenue element with the following attributes:

 totalAmount (optional, data type positive decimal, scale 2) Overall revenue for the currency.

 amount (required, data type positive decimal, scale 2) Overall reseller revenue share.

 purchasePrice (optional, data type positive decimal, scale 2) Difference between the totalAmount and the amount attribute.

Example:

Supplier

Contains the reseller revenue share data for the services provided by a specific supplier.

A Supplier element contains the following subelements:

- An OrganizationData element specifying the details of the supplier organization (see *OrganizationData* on page 62).
- A service element for each service provided by the supplier for which the current reseller organization receives a revenue share (see Service on page 66).
- A ResellerRevenuePerSupplier element with the following attributes:
 totalAmount (optional, data type positive decimal, scale 2) Overall revenue for the supplier.
 amount (required, data type positive decimal, scale 2) Overall reseller revenue share for the supplier.

purchasePrice - (optional, data type positive decimal, scale 2) Difference between the totalAmount and the amount attribute.

Example:

Service

Specifies the reseller revenue share data for a specific service.

A Service element has the following attributes:

- id (required, data type string) Name of the service.
- **key** (required, data type positiveInteger) Internal numeric key of the service offered by the reseller. Technically, this is a copy of the original service defined by the supplier.
- templatekey (required, data type positiveInteger) Internal numeric key of the original service defined by the supplier.

A Service element contains the following subelements:

- A subscription element for each subscription to the service offered by the reseller (see *Subscription* on page 66).
- A ServiceRevenue element specifying the overall reseller revenue share for the service (see ServiceRevenue on page 67).

Example:

Subscription

Specifies the revenue for a specific subscription to a service.

A Subscription element has the following attributes:

- id (required, data type string) Name of the subscription.
- key (required, data type positiveInteger) Internal numeric key of the subscription.
- billingkey (required, data type positiveInteger) Unique identifier allowing, for example, accounting systems to relate billing data to an invoice. The billing data key is printed on the invoice.
- revenue (required, data type positive decimal, scale 2) The total revenue for the subscription in the billing period. Note that there is a Service element for each phase of the subscription if the subscription is upgraded or downgraded.

A Subscription element contains a Period subelement specifying the applicable billing period (see *Period* on page 61).

Example:

```
<Subscription id="Mega Office Basic" key="17005" billingKey="19032"
  revenue="600.00">
  <Period>... </Period>
</Subscription>
```

ServiceRevenue

Specifies the total revenue for a service and the reseller revenue share.

A ServiceRevenue element has the following attributes:

- totalAmount (required, data type positive decimal, scale 2) Total revenue for all subscriptions to the service in the billing period.
- resellerRevenueSharePercentage (required, data type positive decimal, scale 2) Percentage of the revenue the reseller is entitled to.
- resellerRevenue (required, data type positive decimal, scale 2) The reseller's revenue share for the service in the billing period.

A ServiceRevenue element contains a ServiceCustomerRevenue subelement for each customer who used the service. It specifies the total revenue for the service generated by the customer and the reseller revenue share in its attributes:

- customerName (optional, data type string) Name of the customer organization.
- customerId (optional, data type string) ID of the customer organization.
- totalAmount (optional, data type positive decimal, scale 2) Total revenue for the service generated by the customer in the billing period.
- resellerRevenueSharePercentage (optional, data type positive decimal, scale 2) Percentage of the revenue the reseller is entitled to.
- resellerRevenue (optional, data type positive decimal, scale 2) The reseller's revenue share for the service generated by the customer in the billing period.
- purchasePrice (optional, data type positive decimal, scale 2) Difference between the totalAmount and the resellerRevenue attribute.

Example:

B.4 Marketplace Owner Revenue Share Data

The following sections describe the XML elements and attributes that make up the revenue share data for marketplace owners.

MarketplaceOwnerRevenueShareResult

Top-level container element for marketplace owner revenue share data. For each marketplace owner organization in consideration, a MarketplaceOwnerRevenueShareResult element is added to the billing data file.

A MarketplaceOwnerRevenueShareResult element has the following attributes:

- organizationid (required, data type string) ID of the marketplace owner organization.
- organizationKey (required, data type positiveInteger) Internal numeric key of the marketplace owner organization.

A MarketplaceOwnerRevenueShareResult element contains the following subelements:

- An OrganizationData element specifying the details of the marketplace owner organization (see *OrganizationData* on page 62).
- A Period element specifying the billing period (see Period on page 61).
- A Currency element for each currency for which marketplace owner revenue share data is available (see *Currency* on page 68).

Example:

```
<MarketplaceOwnerRevenueShareResult organizationId="cd9ffaac"
  organizationKey="19000">
  <OrganizationData> ... </OrganizationData>
  <Period> ... </Period>
  <Currency> ... </Currency>
</MarketplaceOwnerRevenueShareResult>
```

Currency

Contains the marketplace owner revenue share data for a specific currency.

A currency element has the following attribute:

id - (required, data type string) ISO code of the currency.

A Currency element contains the following subelements:

- A Marketplace element for each marketplace for which revenue share data for the current marketplace owner organization is available (see *Marketplace* on page 68).
- A RevenuesOverAllMarketplaces element summarizing the revenue shares across the marketplaces (see *RevenuesOverAllMarketplaces* on page 72).

Example:

```
<Currency id="EUR">
     <Marketplace>...</Marketplace>
      <RevenuesOverAllMarketplaces> ... </RevenuesOverAllMarketplaces>
</Currency>
```

Marketplace

Contains the revenue share data for a specific marketplace.

A Marketplace element has the following attributes:

- id (required, data type string) ID of the marketplace.
- key (required, data type positiveInteger) Internal numeric key of the marketplace.

A Marketplace element contains the following subelements:

- A Service element for each service published on the marketplace for which revenue share data is available (see *Service* on page 69).
- A RevenuesPerMarketplace element summarizing the revenue shares for all organizations involved (see *RevenuesPerMarketplace* on page 71).

Example:

Service

Specifies the revenue share data for a specific service published on the current marketplace.

A service element has the following attributes:

- id (required, data type string) Name of the service.
- key (required, data type positiveInteger) Internal numeric key of the published service. If
 the service is offered by a broker or reseller, this is the key of an internal technical copy of the
 original service defined by the supplier. If the service is offered directly by its supplier, it is the
 key of the original service.
- model (required, data type string) String specifying by which type of organization the service is offered. Possible values are:
 - DIRECT: The service is offered by its supplier.
 - BROKER: The service is offered by a broker.
 - RESELLER: The service is offered by a reseller.
- templatekey (optional, data type positiveInteger) Internal numeric key of the original service defined by the supplier, if the service is published by a broker or reseller.

A Service element contains the following subelements:

- A Supplier element specifying the supplier organization who defined the service in an OrganizationData subelement (see *OrganizationData* on page 62).
- If the service is offered by a broker: A Broker element specifying the broker organization in an OrganizationData subelement (see *OrganizationData* on page 62).
- If the service is offered by a reseller: A Reseller element specifying the reseller organization in an OrganizationData subelement (see *OrganizationData* on page 62).
- A RevenueShareDetails element specifying the revenue shares for the service (see RevenueShareDetails on page 70).

Examples:

The service is offered directly by its supplier:

The service is offered by a broker:

The service is offered by a reseller:

RevenueShareDetails

Specifies the revenue for a specific service and the revenue shares for all organizations involved in selling the service.

A RevenueShareDetails element has the following attributes:

- serviceRevenue (required, data type decimal, scale 2) Total revenue for the service in the billing period.
- marketplaceRevenueSharePercentage (required, data type decimal, scale 2) Percentage of the revenue the marketplace owner is entitled to.
- operatorRevenueSharePercentage (required, data type decimal, scale 2) Percentage of the revenue the platform operator is entitled to.
- brokerRevenueSharePercentage (optional, data type decimal, scale 2) If the service is offered by a broker: Percentage of the revenue the broker is entitled to.
- resellerRevenueSharePercentage (optional, data type decimal, scale 2) If the service is offered by a reseller: Percentage of the revenue the reseller is entitled to.
- marketplaceRevenue (required, data type decimal, scale 2) The marketplace owner's revenue share for the service in the billing period.
- operatorRevenue (required, data type decimal, scale 2) The platform operator's revenue share for the service in the billing period.
- brokerRevenue (optional, data type decimal, scale 2) If the service is offered by a broker: The broker's revenue share for the service in the billing period.
- resellerRevenue (optional, data type decimal, scale 2) If the service is offered by a reseller: The reseller's revenue share for the service in the billing period.
- amountForSupplier (required, data type decimal, scale 2) The supplier's revenue share for
 the service in the billing period. This is the remaining value of the total service revenue after
 subtracting the revenue shares for the operator, marketplace owner, broker, and/or reseller.

Examples:

The service is offered directly by its supplier:

```
<RevenueShareDetails serviceRevenue="500.00"
  marketplaceRevenueSharePercentage="15.00" marketplaceRevenue="75.00"
  operatorRevenueSharePercentage="10.00" operatorRevenue="50.00"
  amountForSupplier="375.00">
</RevenueShareDetails>
```

The service is offered by a broker:

```
<RevenueShareDetails serviceRevenue="4000.00"
  marketplaceRevenueSharePercentage="21.00" marketplaceRevenue="840.00"
  brokerRevenueSharePercentage="9.00" brokerRevenue="360.00"
  operatorRevenueSharePercentage="5.00" operatorRevenue="200.00"
  amountForSupplier="2600.00">
```

</RevenueShareDetails>

The service is offered by a reseller:

```
<RevenueShareDetails serviceRevenue="3000.00"
  marketplaceRevenueSharePercentage="16.00" marketplaceRevenue="480.00"
  resellerRevenueSharePercentage="20.00" resellerRevenue="600.00"
  operatorRevenueSharePercentage="5.00" operatorRevenue="150.00"
  amountForSupplier="1770.00">
  </RevenueShareDetails>
```

RevenuesPerMarketplace

Provides an overview of the revenue shares for the different organizations involved in selling services on a specific marketplace.

A RevenuesPerMarketplace element contains the following subelements:

- A Brokers element listing the relevant broker organizations with their revenue shares in Organization subelements.
- A Resellers element listing the relevant reseller organizations with their revenue shares in Organization subelements.
- A Suppliers element listing the relevant supplier organizations with their revenue shares in Organization subelements.
- A MarketplaceOwner element specifying the revenue share for the marketplace owner in its amount attribute (required, data type decimal, scale 2).

Each Brokers, Resellers, Or Suppliers element included in a RevenuesPerMarketplace element has the following attributes:

- amount (optional, data type decimal, scale 2) Overall revenue share of the listed broker, reseller, or supplier organizations.
- marketplaceRevenue (optional, data type decimal, scale 2) The marketplace owner's share of the revenue of the listed broker, reseller, or supplier organizations.
- totalAmount (optional, data type decimal, scale 2) Overall revenue for all services offered by the listed broker, reseller, or supplier organizations on the marketplace.

An Organization element included in a Brokers, Resellers, or Suppliers element has the following attributes:

- identifier (required, data type string) ID of the organization.
- amount (required, data type decimal, scale 2) Revenue share of the organization.
- name (optional, data type string) Name of the organization.
- marketplaceRevenue (optional, data type decimal, scale 2) The marketplace owner's share of the organization's revenue.
- totalAmount (optional, data type decimal, scale 2) Overall revenue for all services offered by the organization on the marketplace.

Example:

RevenuesOverAllMarketplaces

Provides an overview of the revenue shares for the different organizations involved in selling services on any of the marketplaces that belong to a specific marketplace owner.

A RevenuesOverAllMarketplaces element contains the following subelements:

- A Brokers element listing the relevant broker organizations with their revenue shares in Organization subelements.
- A Resellers element listing the relevant reseller organizations with their revenue shares in Organization subelements.
- A suppliers element listing the relevant supplier organizations with their revenue shares in Organization subelements.
- A MarketplaceOwner element specifying the revenue share for the marketplace owner in its amount attribute (required, data type decimal, scale 2).

Each Brokers, Resellers, or Suppliers element included in a RevenuesOverAllMarketplaces element has the following attributes:

- amount (optional, data type decimal, scale 2) Overall revenue share of the listed broker, reseller, or supplier organizations.
- marketplaceRevenue (optional, data type decimal, scale 2) The marketplace owner's share of the revenue of the listed broker, reseller, or supplier organizations.
- totalamount (optional, data type decimal, scale 2) Overall revenue for all services offered by the listed broker, reseller, or supplier organizations on the marketplaces.

An Organization element included in a Brokers, Resellers, or Suppliers element has the following attributes:

- identifier (required, data type string) ID of the organization.
- amount (required, data type decimal, scale 2) Revenue share of the organization.
- name (optional, data type string) Name of the organization.
- marketplaceRevenue (optional, data type decimal, scale 2) The marketplace owner's share of the organization's revenue.
- totalAmount (optional, data type decimal, scale 2) Overall revenue for all services offered by the organizations on the marketplaces.

Example:

B.5 Supplier Revenue Share Data

The following sections describe the XML elements and attributes that make up the revenue share data for suppliers.

SupplierRevenueShareResult

Top-level container element for all revenue share data a supplier has to pay to all participating parties (platform operator, marketplace owners, brokers, resellers) based on his contractual agreements. For each supplier organization in consideration, a <code>SupplierRevenueShareResult</code> element is added to the billing data file.

A SupplierRevenueShareResult element has the following attributes:

- organizationId (required, data type string) ID of the supplier organization.
- organizationKey (required, data type positiveInteger) Internal numeric key of the supplier organization.

A SupplierRevenueShareResult element contains the following subelements:

- An OrganizationData element specifying the details of the supplier organization (see *OrganizationData* on page 62).
- A Period element specifying the billing period (see Period on page 61).
- A Currency element for each currency for which supplier revenue share data is available (see *Currency* on page 73).

Example:

```
<SupplierRevenueShareResult organizationId="cd9ffaac"
  organizationKey="19000">
  <OrganizationData> ... </OrganizationData>
  <Period> ... </Period>
  <Currency> ... </Currency>
</supplierRevenueShareResult>
```

Currency

Contains the supplier revenue share data for a specific currency.

A currency element has the following attribute:

id - (required, data type string) ISO code of the currency.

A Currency element contains the following subelements:

- A Marketplace element for each marketplace for which revenue share data for the supplier organization is available (see *Marketplace* on page 74).
- A SupplierRevenue element specifying the detailed revenue share data for the current supplier organization (see *SupplierRevenue* on page 74).

Example:

```
Currency id="EUR">
    <Marketplace>...</Marketplace>
     <SupplierRevenue>...</SupplierRevenue>
</Currency>
```

Marketplace

Contains the revenue share data for a specific marketplace.

A Marketplace element has the following attributes:

- id (required, data type string) ID of the marketplace.
- key (required, data type positiveInteger) Internal numeric key of the marketplace.

A Marketplace element contains the following subelements:

- A MarketplaceOwner element specifying the marketplace owner in an OrganizationData subelement (see *OrganizationData* on page 62).
- A service element for each service published on the marketplace for which revenue share data for the supplier is available (see Service on page 76).
- A RevenuePerMarketplace element summarizing the revenue shares for all organizations involved(see RevenuePerMarketplace on page 80).

Example:

SupplierRevenue

Contains the detailed revenue data for a supplier organization.

A SupplierRevenue element has the following attributes:

• amount - (required, data type decimal, scale 2) Overall revenue for the supplier.

A SupplierRevenue element may contain the following subelements, depending on which organizations offer the supplier's services:

- A DirectRevenue element specifying the revenue for the services offered directly by the supplier.
- A BrokerRevenue element specifying the revenue for the supplier's services offered by brokers.
- A ResellerRevenue element specifying the revenue for the supplier's services offered by resellers.

Example:

DirectRevenue

Contains the revenue data for services offered directly by their supplier.

A DirectRevenue element has the following attributes:

- serviceRevenue (required, data type decimal, scale 2) Overall revenue for the services offered by the supplier.
- marketplaceRevenue (required, data type decimal, scale 2) Overall revenue for the owners of the marketplaces where the services are offered by the supplier.
- operatorRevenue (required, data type decimal, scale 2) Overall revenue for the platform operator who provides the infrastructure for the marketplaces and services.

Example:

BrokerRevenue

Contains the revenue data for a supplier's services offered by brokers.

A BrokerRevenue element has the following attributes:

- serviceRevenue (required, data type decimal, scale 2) Overall revenue for the services offered by the broker.
- marketplaceRevenue (required, data type decimal, scale 2) Overall revenue for the owners of the marketplaces where the services are offered by brokers.
- brokerRevenue (required, data type decimal, scale 2) Overall revenue share for the broker offering the services.
- operatorRevenue (required, data type decimal, scale 2) Overall revenue for the platform operator who provides the infrastructure for the marketplaces and services.

Example:

ResellerRevenue

Contains the revenue data for the supplier's services offered by resellers.

A ResellerRevenue element has the following attributes:

- serviceRevenue (required, data type decimal, scale 2) Overall revenue for the services offered by resellers.
- marketplaceRevenue (required, data type decimal, scale 2) Overall revenue for the owners of the marketplaces where the services are offered by the resellers.
- resellerRevenue (required, data type decimal, scale 2) Overall revenue share for the resellers offering the services.
- operatorRevenue (required, data type decimal, scale 2) Overall revenue for the platform operator who provides the infrastructure for the marketplaces and services.
- overallRevenue (required, data type decimal, scale 2) Overall revenue for the services offered by the resellers minus the marketplace owner revenue (marketplaceRevenue), the reseller revenue (resellerRevenue), and the operator revenue (operatorRevenue).

Example:

Service

Specifies the revenue share data for a specific service.

A Service element has the following attributes:

- id (required, data type string) Name of the service.
- key (required, data type positiveInteger) Internal numeric key of the published service. If the service is offered by a broker or reseller, this is the key of an internal technical copy of the original service defined by the supplier. If the service is offered directly by its supplier, it is the key of the original service.
- model (required, data type string) String specifying by which type of organization the service is offered. Possible values are:
 - DIRECT: The service is offered by its supplier.
 - BROKER: The service is offered by a broker.
 - RESELLER: The service is offered by a reseller.
- templatekey (optional, data type positiveInteger) Internal numeric key of the original service defined by the supplier, if the service is published by a broker or reseller.

A Service element contains the following subelements:

- If the service is offered directly by the supplier: A Subscription element for each subscription to the service for which revenue share data is available (see *Subscription* on page 77).
- If the service is offered by a broker:
 - A subscription element for each subscription to the service for which revenue share data is available (see *Subscription* on page 77).

- A Broker element specifying the broker organization in an OrganizationData subelement (see *OrganizationData* on page 62).
- If the service is offered by a reseller:
 - A SubscriptionsRevenue element summarizing the total revenue for all subscriptions to the service in its amount attribute (required, data type positive decimal, scale 2).
 - A Reseller element specifying the reseller organization in an OrganizationData subelement (see *OrganizationData* on page 62).
- A RevenueShareDetails element specifying the revenue shares for the service (see RevenueShareDetails on page 78).

Examples:

The service is offered directly by its supplier:

The service is offered by a broker:

The service is offered by a reseller:

Subscription

Specifies the revenue for a specific subscription to a service.

A Subscription element has the following attributes:

- id (required, data type string) Name of the subscription.
- key (required, data type positiveInteger) Internal numeric key of the subscription.
- billingkey (required, data type positiveInteger) Unique identifier allowing, for example, accounting systems to relate billing data to an invoice. The billing data key is printed on the invoice.
- revenue (required, data type positive decimal, scale 2) The total revenue for the subscription in the billing period. Note that there is a Service element for each phase of the subscription if the subscription is upgraded or downgraded.

A Subscription element contains a Period subelement specifying the applicable billing period (see *Period* on page 61).

Example:

```
<Subscription id="Mega Office Basic" key="17005" billingKey="19032"
  revenue="600.00">
  <Period>... </Period>
</Subscription>
```

RevenueShareDetails

Specifies the revenue for a specific service and the revenue shares for all organizations involved in selling the service.

A RevenueShareDetails element has the following attributes:

- serviceRevenue (required, data type decimal, scale 2) Total revenue for the service in the billing period.
- marketplaceRevenueSharePercentage (required, data type decimal, scale 2) Percentage of the revenue the marketplace owner is entitled to.
- brokerRevenueSharePercentage (optional, data type decimal, scale 2) If the service is offered by a broker: Percentage of the revenue the broker is entitled to.
- resellerRevenueSharePercentage (optional, data type decimal, scale 2) If the service is offered by a reseller: Percentage of the revenue the reseller is entitled to.
- marketplaceRevenue (required, data type decimal, scale 2) The marketplace owner's revenue share for the service in the billing period.
- brokerRevenue (optional, data type decimal, scale 2) If the service is offered by a broker: The broker's revenue share for the service in the billing period.
- resellerRevenue (optional, data type decimal, scale 2) If the service is offered by a reseller: The reseller's revenue share for the service in the billing period.
- operatorRevenueSharePercentage (required, data type decimal, scale 2) Percentage of the revenue the operator is entitled to.
- operatorRevenue (required, data type decimal, scale 2) The operator's revenue share for the service in the billing period.
- amountForsupplier (required, data type decimal, scale 2) The supplier's revenue share for the service in the billing period. This is the remaining value of the total service revenue after subtracting the revenue shares for the operator, marketplace owner, broker, and/or reseller.

A RevenueShareDetails element contains a CustomerRevenueShareDetails subelement for each customer who used the service (see *CustomerRevenueShareDetails* on page 79).

Examples:

The service is offered directly by its supplier:

```
<RevenueShareDetails serviceRevenue="500.00"
   marketplaceRevenueSharePercentage="15.00" marketplaceRevenue="75.00"
   operatorRevenueSharePercentage="10.00" operatorRevenue="50.00"
   amountForSupplier="375.00">
        <CustomerRevenueShareDetails> ... </CustomerRevenueShareDetails>
        </RevenueShareDetails>
```

The service is offered by a broker:

```
<RevenueShareDetails serviceRevenue="4000.00"
   marketplaceRevenueSharePercentage="21.00" marketplaceRevenue="840.00"
   brokerRevenueSharePercentage="9.00" brokerRevenue="360.00"</pre>
```

The service is offered by a reseller:

```
<RevenueShareDetails serviceRevenue="3000.00"
   marketplaceRevenueSharePercentage="16.00" marketplaceRevenue="480.00"
   resellerRevenueSharePercentage="20.00" resellerRevenue="600.00"
   operatorRevenueSharePercentage="10.00" operatorRevenue="300.00"
   amountForSupplier="1620.00">
        <CustomerRevenueShareDetails> ... </CustomerRevenueShareDetails><//r>
```

CustomerRevenueShareDetails

Specifies the revenue for a specific service generated by a given customer and the revenue shares for all organizations involved in selling the service.

A CustomerRevenueShareDetails element has the following attributes:

- customerName (required, data type string) Name of the customer organization.
- customerId (required, data type string) ID of the customer organization.
- serviceRevenue (required, data type decimal, scale 2) Total revenue for the service in the billing period.
- marketplaceRevenue (required, data type decimal, scale 2) The marketplace owner's revenue share for the service in the billing period.
- resellerRevenue (optional, data type decimal, scale 2) If the service is offered by a reseller: The reseller's revenue share for the service in the billing period.
- brokerRevenue (optional, data type decimal, scale 2) If the service is offered by a broker: The broker's revenue share for the service in the billing period.
- operatorRevenue (required, data type decimal, scale 2) The operator's revenue share for the service in the billing period.
- amountForsupplier (required, data type decimal, scale 2) The supplier's revenue share for
 the service generated by the customer in the billing period. This is the remaining value of the
 total service revenue generated by the customer after subtracting the revenue shares for the
 operator, marketplace owner, broker, and/or reseller.

Examples:

The service is offered directly by its supplier:

```
<CustomerRevenueShareDetails customerName="MyCompany"
  customerId="8dac00a0" serviceRevenue="316.92"
  marketplaceRevenue="31.69" operatorRevenue="31.69"
  amountForSupplier="223.54"/>
```

The service is offered by a broker:

```
<CustomerRevenueShareDetails customerName="ITCompany"
  customerId="ff48ae0b" serviceRevenue="300.00"
  marketplaceRevenue="63.00" brokerRevenue="27.00"
  operatorRevenue="30.00" amountForSupplier="180.00" />
```

The service is offered by a reseller:

```
<CustomerRevenueShareDetails customerName="YourCompany"
  customerId="859069d7" serviceRevenue="500.00"
  marketplaceRevenue="80.00" resellerRevenue="250.00"
  operatorRevenue="50.00" amountForSupplier="120.00"/>
```

RevenuePerMarketplace

Provides an overview of the revenue shares for the different organizations involved in selling the services of a supplier on a specific marketplace.

A RevenuePerMarketplace element has the following attributes:

- serviceRevenue (required, data type decimal, scale 2) Total revenue for all relevant services in the billing period.
- marketplaceRevenue (required, data type decimal, scale 2) Total revenue share for the marketplace owner.
- brokerRevenue (optional, data type decimal, scale 2) Total revenue share for all brokers.
- resellerRevenue (optional, data type decimal, scale 2) Total revenue share for all resellers.
- operatorRevenue (required, data type decimal, scale 2) Total revenue share for the operator.
- overallRevenue (required, data type decimal, scale 2) Total revenue for the supplier. This is the remaining value of the total revenue for all services after subtracting the revenue shares for the operator, marketplace owner, brokers, and/or resellers.

Example:

```
<RevenuePerMarketplace serviceRevenue="80905.00"
  marketplaceRevenue="8090.50"
  resellerRevenue="0.00"
  brokerRevenue="20226.25"
  operatorRevenue="8899.55"
  overallRevenue="43688.70"/>
```

Glossary

Administrator

A privileged user role within an organization with the permission to manage the organization's account and subscriptions as well as its users and their roles. Each organization has at least one administrator.

Application

A software, including procedures and documentation, which performs productive tasks for users.

Broker

An organization which supports suppliers in establishing relationships to customers by offering the suppliers' services on a marketplace, as well as a privileged user role within such an organization.

Cloud

A metaphor for the Internet and an abstraction of the underlying infrastructure it conceals.

Cloud Computing

The provisioning of dynamically scalable and often virtualized resources as a service over the Internet on a utility basis.

Customer

An organization which subscribes to one or more marketable services in CT-MG in order to use the underlying applications in the Cloud.

Infrastructure as a Service (laaS)

The delivery of computer infrastructure (typically a platform virtualization environment) as a service.

Marketable Service

A service offering to customers in CT-MG, based on a technical service. A marketable service defines prices, conditions, and restrictions for using the underlying application.

Marketplace

A virtual platform for suppliers, brokers, and resellers in CT-MG to provide their services to customers.

Marketplace Owner

An organization which holds a marketplace in CT-MG, where one or more suppliers, brokers, or resellers can offer their marketable services.

Marketplace Manager

A privileged user role within a marketplace owner organization.

Operator

An organization or person responsible for maintaining and operating CT-MG.

Organization

An organization typically represents a company, but it may also stand for a department of a company or a single person. An organization has a unique account and ID, and is assigned one or more of the following roles: technology provider, supplier, customer, broker, reseller, marketplace owner, operator.

Payment Service Provider (PSP)

A company that offers suppliers or resellers online services for accepting electronic payments by a variety of payment methods including credit card or bank-based payments such as direct debit or bank transfer. Suppliers and resellers can use the services of a PSP for the creation of invoices and payment collection.

Payment Type

A specification of how a customer may pay for the usage of his subscriptions. The operator defines the payment types available in CT-MG; the supplier or reseller determines which payment types are offered to his customers, for example payment on receipt of invoice, direct debit, or credit card.

Platform as a Service (PaaS)

The delivery of a computing platform and solution stack as a service.

Price Model

A specification for a marketable service defining whether and how much customers subscribing to the service will be charged for the subscription as such, each user assigned to the subscription, specific events, or parameters and their options.

Reseller

An organization which offers services defined by suppliers to customers applying its own terms and conditions, as well as a privileged user role within such an organization.

Role

A collection of authorities that control which actions can be carried out by an organization or user to whom the role is assigned.

Seller

Collective term for supplier, broker, and reseller organizations.

Service

Generally, a discretely defined set of contiguous or autonomous business or technical functionality, for example an infrastructure or Web service. CT-MG distinguishes between technical services and marketable services, and uses the term "service" as a synonym for "marketable service".

Service Manager

A privileged user role within a supplier organization.

Standard User

A non-privileged user role within an organization.

Software as a Service (SaaS)

A model of software deployment where a provider licenses an application to customers for use as a service on demand.

Subscription

An agreement registered by a customer for a marketable service in CT-MG. By subscribing to a service, the customer is given access to the underlying application under the conditions defined in the marketable service.

Subscription Manager

A privileged user role within an organization with the permission to create and manage his own subscriptions.

Supplier

An organization which defines marketable services in CT-MG for offering applications provisioned by technology providers to customers.

Technical Service

The representation of an application in CT-MG. A technical service describes parameters and interfaces of the underlying application and is the basis for one or more marketable services.

Technology Manager

A privileged user role within a technology provider organization.

Technology Provider

An organization which provisions applications as technical services in CT-MG.

User Group

A set of one or more users representing, for example, a department in a company, an individual project, or a single person. Groups provide a means to restrict the visibility of services on a marketplace.