

FUJITSU Software PRIMECLUSTER GD Snapshot 4.5A00

A decorative horizontal band with a red-to-dark-red gradient, featuring abstract white and light red curved lines and glowing points.

Installation Guide

Linux

J2UL-2274-01ENZ0(00)
December 2017

Preface

Purpose

This manual explains how to install PRIMECLUSTER GD Snapshot.

Target Readers

This manual is written for people who will install this product.

It is strongly recommended that you read the Software Release Guide before using this manual.

When setting up systems, it is assumed that readers have the basic knowledge required to configure the servers, storage and network devices to be installed.

Organization

This manual consists of four chapters, and appendices. The contents of these chapters, the appendices are listed below.

Title	Description
Chapter 1 Program components	Explains the packages of which this product is composed.
Chapter 2 Operation Environment	Explains the operational environment of this product.
Chapter 3 Installation	Explains how to install this product.
Chapter 4 Uninstallation	Explains how to uninstall this product.
Appendix A Troubleshooting	Explains how to address problems that occur.

Notational Conventions

The notation in this manual conforms to the following conventions.

- References and character strings or values requiring emphasis are indicated using double quotes (").
- Text to be entered by the user is indicated using bold text.
- Variables are indicated using italic text.

The following abbreviation is used in this manual:

- Global Disk Services is abbreviated as GDS.
- PRIMEQUEST 3000/2000 Series is abbreviated as PRIMEQUEST.

Export Administration Regulation Declaration

Exportation/release of this document may require necessary procedures in accordance with the regulations of your resident country and/or US export control laws.

Trademark Information

- Linux is a registered trademark of Linus Torvalds.
- Red Hat is a registered trademark of Red Hat, Inc. in the U.S. and other countries.
- Other trademarks and registered trademarks appearing in this manual are the trademarks or registered trademarks of their owners.

Information in this manual is subject to change without notice.



The latest manuals are available at

Date of publication and edition

Date of publication and edition	Manual code
December 2017, First edition	J2UL-2274-01ENZ0(00)/J2UL-2274-01ENZ2(00)

Copyright notice

All Rights Reserved, Copyright (C) FUJITSU LIMITED 2017

Revision History

First edition

Contents

Chapter 1 Program components.....	1
1.1 Red Hat Enterprise Linux 6 (for Intel64) for PRIMERGY/PRIMEQUEST.....	1
1.2 Red Hat Enterprise Linux 7 (for Intel64) for PRIMERGY/PRIMEQUEST.....	1
Chapter 2 Operation Environment.....	2
2.1 Software environment.....	2
2.2 Hardware environment.....	3
2.3 Static disk resources.....	3
2.3.1 Required disk space.....	3
2.3.2 Required work area.....	3
2.4 Dynamic disk resources.....	3
2.5 Required memory.....	4
Chapter 3 Installation.....	5
3.1 Preparations.....	5
3.2 Installation.....	5
3.3 Environment configuration.....	6
Chapter 4 Uninstallation.....	7
4.1 Preparation.....	7
4.2 Uninstallation.....	7
Appendix A Troubleshooting.....	8
A.1 When segmentation violation causes an installation failure.....	8

Chapter 1 Program components

The unit of the program that composes the system is called a package.
This chapter explains about the packages of which this software is composed.

PRIMERGY

- Red Hat Enterprise Linux 6 (for Intel64)
- Red Hat Enterprise Linux 7 (for Intel64)

PRIMEQUEST

- Red Hat Enterprise Linux 6 (for Intel64)
- Red Hat Enterprise Linux 7 (for Intel64)

1.1 Red Hat Enterprise Linux 6 (for Intel64) for PRIMERGY/ PRIMEQUEST

No.	Component	Package	Version	Function
1	Global Disk Services(GDS) Snapshot	FJSVsdx-ss	4.5.0	GDS Snapshot option
		FJSVsdx-bss	4.5.0	
		FJSVgdapi	1.18	

1.2 Red Hat Enterprise Linux 7 (for Intel64) for PRIMERGY/ PRIMEQUEST

No.	Component	Package	Version	Function
1	Global Disk Services(GDS) Snapshot	FJSVsdx-ss	4.5.0	GDS Snapshot option
		FJSVsdx-bss	4.5.0	
		FJSVgdapi	1.21	

Chapter 2 Operation Environment

This chapter explains the operation environment of this software.

2.1 Software environment

1. Basic software prerequisites

This software is option software of PRIMECLUSTER 4.5A00.

A basic software necessary for operating this software is the same as a basic software necessary for operating PRIMECLUSTER 4.5A00 for Linux(TM).

2. Required software

To operate this software, the following software products are required:

1. Red Hat Enterprise Linux 6 (for Intel64) for PRIMERGY

No.	Software	Package	Version and/or level	Remarks
1	PRIMECLUSTER Enterprise Edition or PRIMECLUSTER HA Server	FJSVsdx-bas	4.5.0	
		FJSVsdx-cmd	4.5.0	
		FJSVsdx-drv	4.5.0	
		kmod-FJSVsdx-drvcore	4.5.0	

2. Red Hat Enterprise Linux 7 (for Intel64) for PRIMERGY

No.	Software	Package	Version and/or level	Remarks
1	PRIMECLUSTER Enterprise Edition or PRIMECLUSTER HA Server	FJSVsdx-bas	4.5.0	
		FJSVsdx-cmd	4.5.0	
		FJSVsdx-drv	4.5.0	
		kmod-FJSVsdx-drvcore	4.5.0	

3. Red Hat Enterprise Linux 6 (for Intel64) for PRIMEQUEST

No.	Software	Package	Version and/or level	Remarks
1	PRIMECLUSTER Enterprise Edition or PRIMECLUSTER HA Server or PRIMECLUSTER GD	FJSVsdx-bas	4.5.0	
		FJSVsdx-cmd	4.5.0	
		FJSVsdx-drv	4.5.0	
		kmod-FJSVsdx-drvcore	4.5.0	

4. Red Hat Enterprise Linux 7 (for Intel64) for PRIMEQUEST

No.	Software	Package	Version and/or level	Remarks
1	PRIMECLUSTER Enterprise Edition or PRIMECLUSTER HA Server or PRIMECLUSTER GD	FJSVsdx-bas	4.5.0	
		FJSVsdx-cmd	4.5.0	
		FJSVsdx-drv	4.5.0	
		kmod-FJSVsdx-drvcore	4.5.0	

3. Exclusive software

None.

4. Required patches

None.

2.2 Hardware environment

The following hardware requirements must be satisfied to operate this software.

1. Memory

1024MB or more of memory is required.

2. Required hardware

None.

2.3 Static disk resources

This section explains static disk space requirements for this software.

2.3.1 Required disk space

The following table lists the disk space requirements for installing this software. If necessary, expand the size of the relevant file systems.

No.	Directory	Disk space (in MB)	Remarks
1	/	0.0	
2	/usr	0.0	
3	/var	1.8	
4	/etc	0.0	
5	/etc/opt	0.6	
6	/opt	1.7	

2.3.2 Required work area

None.

2.4 Dynamic disk resources

None.

2.5 Required memory

The following table shows the memory required when this software is operated in the following environment:

No.	Memory (in MB)	Operation
1	41.0	sdxproxy operated, and proxy volume is configured.

Chapter 3 Installation

This chapter explains the installation of this software.

If the basic packages for PRIMECLUSTER GD, FJSVsdx-bas, FJSVsdx-cmd, and FJSVsdx-drv, are not installed, the product cannot be installed. All packages are included in No.1 of "2) Required software" of "2.1 Software environment".

3.1 Preparations

1. Prerequisites

Make sure that the disk has enough free space to install this software. For the disk size that this software uses, see "2.3 Static disk resources". If free space is insufficient, re-configure the disk partitions.

1. Check the auto startup of the NetworkManager service.

PRIMECLUSTER does not support the NetworkManager service.

Check the auto startup of the NetworkManager service setting.

[Red Hat Enterprise Linux 6]

Check that the setting of auto startup of the NetworkManager service is "off" using the following command.

```
# /sbin/chkconfig --list NetworkManager <Return>
NetworkManager 0:off 1:off 2:off 3:off 4:off 5:off 6:off
```

If there is runlevel that is in "on", disable the NetworkManager service using the following command.

```
# /sbin/service NetworkManager stop
# /sbin/chkconfig NetworkManager off
```

[Red Hat Enterprise Linux 7]

Check that the setting of auto startup of the NetworkManager service is "disabled" using the following command.

```
# /usr/bin/systemctl is-enabled NetworkManager.service <Return>
disabled
```

If the setting is "enabled", disable the NetworkManager service using the following command.

```
# /usr/bin/systemctl stop NetworkManager.service <Return>
# /usr/bin/systemctl disable NetworkManager.service <Return>
```

2. Saving the configuration file

None.

3. Time required

It takes approximately 5 minutes to install this software.

3.2 Installation

1. Login to the system and become the root user.

```
$ su <Return>
Password:password <Return>
```

2. Insert CD in the CD-ROM drive.

```
# mount /media/cdrom <Return>
```

<CDROM_DIR> will be used as the mount point.

3. Install the packages by executing the rpm(8) command.



Notes in the case of upgrading from the old version to this version:

- If the rpm has already installed and the version is same or newer than the rpm in the CD-ROM, don't install it.
- If the rpm has already installed and the version is older than the rpm in the CD-ROM, execute the rpm(8) command with "-Uhv" options, not with "-ihv" options.

Red Hat Enterprise Linux 6 (for Intel64)

```
# cd <CDROM_DIR>/Linux/products/GDS_Snapshot_RH_EL6_x86_64/i386 <Return>
# rpm -ihv FJSVsdx-ss-4.5.0-X.rhel6_x86_64.rpm <Return>
# rpm -ihv FJSVsdx-bss-4.5.0-X.rhel6_x86_64.rpm <Return>
# rpm -ihv FJSVgdapi-1.18-X.x86_64.rpm <Return>
```

Red Hat Enterprise Linux 7 (for Intel64)

```
# cd <CDROM_DIR>/Linux/products/GDS_Snapshot_RH_EL7_x86_64/i386 <Return>
# rpm -ihv FJSVsdx-ss-4.5.0-X.rhel7_x86_64.rpm <Return>
# rpm -ihv FJSVsdx-bss-4.5.0-X.rhel7_x86_64.rpm <Return>
# rpm -ihv FJSVgdapi-1.21-X.x86_64.rpm <Return>
```



The number entered for 'X' corresponds to that of the package.

4. Eject the CD.

```
# cd / <Return>
# umount /media/cdrom <Return>
# eject <Return>
```

5. Download patch(es)

Download the latest patch(es) for this software and update information file from Updatesite.

6. Apply the patch(es) for this software.

For installation instructions and pints of concern, etc., refer to the update information file of each patch.

3.3 Environment configuration

Refer to "PRIMECLUSTER Global Disk Services Configuration and Administration Guide."

Chapter 4 Uninstallation

This chapter explains the uninstallation of this software.

4.1 Preparation

Before uninstalling, if you are applying patch for PRIMECLUSTER by UpdateSite format, remove them by UpdateAdvisor (middleware).

For details, see help information on UpdateAdvisor(middleware) and the update information file of the patch.

4.2 Uninstallation

If you are using a proxy volume, unconfigure the proxy volume by executing the sdxproxy Break command.

1. Login to the system as the root user.

```
$ su <Return>
Password:password <Return>
```

2. Remove the package using the rpm(8) command.

```
# rpm -e FJSVgdapi <Return>
# rpm -e FJSVsdx-bss <Return>
# rpm -e FJSVsdx-ss <Return>
```

Appendix A Troubleshooting

This chapter explains how to address problems that occur.

A.1 When segmentation violation causes an installation failure

If segmentation violation is due to the rpm(8) command, take the following corrective steps. If the problem still remains unresolved, contact Fujitsu customer support engineers.

1. Reboot the system by executing the shutdown(8) command.

```
# shutdown -r now <Return>
```

2. Delete PRIMECLUSTER GD Snapshot from the system according to "[4.2 Uninstallation](#)".
3. Execute the following command.

```
# rpm --rebuilddb <Return>
```

4. Install PRIMECLUSTER GD Snapshot again.